

RH850/D1x Device Family Renesas Graphics Library Video Output Checker A (VOCA) Driver User's Manual: Software

All information contained in these materials, including products and product specifications, represents information on the product at the time of publication and is subject to change by Renesas Electronics Corp. without notice. Please review the latest information published by Renesas Electronics Corp. through various means, including the Renesas Electronics Corp. website (http://www.renesas.com).

Notice

- 1. Descriptions of circuits, software and other related information in this document are provided only to illustrate the operation of semiconductor products and application examples. You are fully responsible for the incorporation or any other use of the circuits, software, and information in the design of your product or system. Renesas Electronics disclaims any and all liability for any losses and damages incurred by you or third parties arising from the use of these circuits, software, or information.
- 2. Renesas Electronics hereby expressly disclaims any warranties against and liability for infringement or any other claims involving patents, copyrights, or other intellectual property rights of third parties, by or arising from the use of Renesas Electronics products or technical information described in this document, including but not limited to, the product data, drawings, charts, programs, algorithms, and application examples.
- 3. No license, express, implied or otherwise, is granted hereby under any patents, copyrights or other intellectual property rights of Renesas Electronics or others.
- 4. You shall not alter, modify, copy, or reverse engineer any Renesas Electronics product, whether in whole or in part. Renesas Electronics disclaims any and all liability for any losses or damages incurred by you or third parties arising from such alteration, modification, copying or reverse engineering.
- 5. Renesas Electronics products are classified according to the following two quality grades: "Standard" and "High Quality". The intended applications for each Renesas Electronics product depends on the product's quality grade, as indicated below.
 - "Standard": Computers; office equipment; communications equipment; test and measurement equipment; audio and visual equipment; home electronic appliances; machine tools; personal electronic equipment; industrial robots; etc.
 - "High Quality": Transportation equipment (automobiles, trains, ships, etc.); traffic control (traffic lights); large-scale communication equipment; key financial terminal systems; safety control equipment; etc.
 - Unless expressly designated as a high reliability product or a product for harsh environments in a Renesas Electronics data sheet or other Renesas Electronics document, Renesas Electronics products are not intended or authorized for use in products or systems that may pose a direct threat to human life or bodily injury (artificial life support devices or systems; surgical implantations; etc.), or may cause serious property damage (space system; undersea repeaters; nuclear power control systems; aircraft control systems; key plant systems; military equipment; etc.). Renesas Electronics disclaims any and all liability for any damages or losses incurred by you or any third parties arising from the use of any Renesas Electronics product that is inconsistent with any Renesas Electronics data sheet, user's manual or other Renesas Electronics document.
- 6. When using Renesas Electronics products, refer to the latest product information (data sheets, user's manuals, application notes, "General Notes for Handling and Using Semiconductor Devices" in the reliability handbook, etc.), and ensure that usage conditions are within the ranges specified by Renesas Electronics with respect to maximum ratings, operating power supply voltage range, heat dissipation characteristics, installation, etc. Renesas Electronics disclaims any and all liability for any malfunctions, failure or accident arising out of the use of Renesas Electronics products outside of such specified ranges.
- 7. Although Renesas Electronics endeavors to improve the quality and reliability of Renesas Electronics products, semiconductor products have specific characteristics, such as the occurrence of failure at a certain rate and malfunctions under certain use conditions. Unless designated as a high reliability product or a product for harsh environments in a Renesas Electronics data sheet or other Renesas Electronics document, Renesas Electronics products are not subject to radiation resistance design. You are responsible for implementing safety measures to guard against the possibility of bodily injury, injury or damage caused by fire, and/or danger to the public in the event of a failure or malfunction of Renesas Electronics products, such as safety design for hardware and software, including but not limited to redundancy, fire control and malfunction prevention, appropriate treatment for aging degradation or any other appropriate measures. Because the evaluation of microcomputer software alone is very difficult and impractical, you are responsible for evaluating the safety of the final products or systems manufactured by you.
- 8. Please contact a Renesas Electronics sales office for details as to environmental matters such as the environmental compatibility of each Renesas Electronics product. You are responsible for carefully and sufficiently investigating applicable laws and regulations that regulate the inclusion or use of controlled substances, including without limitation, the EU RoHS Directive, and using Renesas Electronics products in compliance with all these applicable laws and regulations. Renesas Electronics disclaims any and all liability for damages or losses occurring as a result of your noncompliance with applicable laws and regulations.
- 9. Renesas Electronics products and technologies shall not be used for or incorporated into any products or systems whose manufacture, use, or sale is prohibited under any applicable domestic or foreign laws or regulations. You shall comply with any applicable export control laws and regulations promulgated and administered by the governments of any countries asserting jurisdiction over the parties or transactions.
- 10. It is the responsibility of the buyer or distributor of Renesas Electronics products, or any other party who distributes, disposes of, or otherwise sells or transfers the product to a third party, to notify such third party in advance of the contents and conditions set forth in this document.
- 11. This document shall not be reprinted, reproduced or duplicated in any form, in whole or in part, without prior written consent of Renesas Electronics.
- 12. Please contact a Renesas Electronics sales office if you have any questions regarding the information contained in this document or Renesas Electronics products.
- (Note 1) "Renesas Electronics" as used in this document means Renesas Electronics Corporation and also includes its directly or indirectly controlled subsidiaries.
- (Note 2) "Renesas Electronics product(s)" means any product developed or manufactured by or for Renesas Electronics.

Trademark

- Green Hills, the Green Hills logo, INTEGRITY, MULTI, DoubleCheck, EventAnalyzer, Integrate,
 SuperTrace, ResourceAnalyzer, CodeFactor, INTEGRITY MULTIvisor, GMART, GSTART, G-Cover,
 PathAnalyzer, GHNet, TimeMachine, μ-velOSity, Padded Cell, TotalDeveloper, and Optimizing Compiler
 are trademarks or registered trademarks of Green Hills Software in the US and/or internationally.
- This software contains the technology owned by TES Electronic Solutions GmbH. All rights reserved for TES Electronic Solutions GmbH
- Trademarks and trademark symbols (® or TM) are omitted in the text of this manual.

How to Use This Manual

1. Purpose and Target Readers

This manual is designed to provide the user with an understanding the functions of VOCA dirver. This manual is written for engineers who use VOCA driver.

Particular attention should be paid to the precautionary notes when using the manual. These notes occur within the body of the text, at the end of each section, and in the Usage Notes section.

The revision history summarizes the locations of revisions and additions. It does not list all revisions. Refer to the text of the manual for details.

Please refer to documents of drivers and hardware for a target system implementing VOCA as necessary.

The following documents are related documents. Make sure to refer to the latest versions of these documents.

| Document Type | Description | Document Title | Document No. |
|-------------------------------|---|--|---------------------------------|
| User's manual for Hardware | Hardware specifications (pin assignments, memory maps, peripheral function specifications, electrical characteristics, timing charts) and operation description | RH850/D1L/D1M Group User's Manual: Hardware | R01UH0451EJ0220 |
| User's manual for Software | Description of RGL overview | Renesas Graphics Library User's Manual: Software | R01US0181ED0400 |
| | Description of WM | Renesas Graphics Library Window Manager (WM) Driver User's Manual: Software | LLWEB-10035990 |
| | Description of SPEA | Renesas Graphics Library Sprite Engine A (SPEA) Driver User's Manual: Software | LLWEB-10035991 |
| | Description of VDCE | Renesas Graphics Library Video Data Controller E (VDCE) Driver User's Manual: Software | LLWEB-10035992 |
| | Description of VOWE | Renesas Graphics Library Video Output Warping Engine (VOWE) Driver User's Manual: Software | LLWEB-10035993 |
| | Description of JCUA | Renesas Graphics Library JPEG Codec Unit A (JCUA) Driver User's Manual: Software | LLWEB-10035994 |
| | Description of SFMA | Renesas Graphics Library Serial Flash Memory Interface A (SFMA) Driver User's Manual: Software | LLWEB-10064753 |
| | Description of HYPB | Renesas Graphics Library HyperBus Controller (HYPB) Driver User's Manual: Software | LLWEB-10064754 |
| | Description of OCTA | Renesas Graphics Library OctaBus Controller (OCTA) Driver User's Manual: Software | LLWEB-10064755 |
| | Description of VOCA | Renesas Graphics Library Video Output Checker A (VOCA) Driver User's Manual: Software | LLWEB-10063801 (This manual) |

| | Description of DISCOM | Renesas Graphics Library Display Output Comparator (DISCOM) Driver User's Manual: Software | LLWEB-10063802 |
|------------------------|-------------------------------------|--|----------------|
| | Description of DRW2D | Renesas Graphics Library 2D Graphics (DRW2D) Driver User's Manual: Software | LLWEB-10059472 |
| Porting Layer Guide | Description of porting layer of RGL | Renesas Graphics Library Porting Layer Guide | LLWEB-10035995 |

2. Notation of Numbers and Symbols

This manual uses the following notation.

 $\begin{array}{lll} Binary & 0bXXXXXXXX & (X=0 \ or \ 1) \\ Decimal \ XXX & (X=0-9) \\ Hex & 0xXXXXXXXX & (X=0-9,A-F) \end{array}$

3. List of Abbreviations and Acronyms

| Abbreviation | Full Form |
|--------------|---|
| API | Application Programming Interface |
| bpp | bit per pixel |
| CLUT | Color Look Up table |
| CPU | Central Processing Unit. The microprocessor core of the LSI. |
| DISCOM | Display Output Comparator |
| ECM | Error Control Module |
| H/W | Hardware |
| VDCE | Video Data Controller E. This is H/W, which controls video input, image synthesis and video output. |
| VOCA | Video Output Checker A. |

All trademarks and registered trademarks are the property of their respective owners.

Table of Contents

Renesas Graphics Library Video Output Checker A (VOCA) Driver

| 1. O | verview | | 3 |
|-------------|--------------|---|----|
| 1.1 | Feature and | Scope | 3 |
| 1.2 | Component | Structure | 3 |
| | | | |
| 2. B | | cation | |
| 2.1 | | pecification | |
| 2.2 | | /ord | |
| 2.3 | | andler List | |
| 2.4 | | ling | |
| 2 | | rn code | |
| | 2.4.1.1 | Parameter level | |
| | 2.4.1.2 | Timing level | |
| | 2.4.1.3 | System level | |
| 2.5 | 2.4.1.4 | Hardware leveltion | |
| 2.3 | State Transi | | |
| 2 E | umation Dag | cription | 0 |
| э. г 3.1 | | al Concepts | |
| | | 'A unit | |
| _ | | o channel | |
| | | o Output Monitor | |
| | | o Output Monitoring | |
| | | riminator calculation | |
| _ | | itoring sequence | |
| | | vity Monitor | |
| | | PI | |
| | | alization / De-Initialization | |
| | | lay Area | |
| | 1 | o Output Monitor area | |
| | | rence color | |
| | | Video Output Monitor Check Enable / Disable | |
| | | Activity Monitor Enable / Disable | |
| 3.3 | | erence | |
| 3.4 | | List | |
| | | | |
| 4. Fi | unctions | | 18 |
| 4.1 | Function Lis | st | 18 |
| 4.2 | VOCA API | Functions | 19 |
| 4 | .2.1 Basic | c functions | 19 |
| | 4.2.1.1 | R_VOCA_Init | 19 |
| | 4.2.1.2 | R_VOCA_DeInit | 21 |
| | 4.2.1.3 | R_VOCA_ErrorCallbackSet | 23 |
| | 4.2.1.4 | R_VOCA_ParamSet | 25 |
| | 4.2.1.5 | R_VOCA_ActiveMonitorEnable | 27 |
| | 4.2.1.6 | R_VOCA_ActiveMonitorDisable | 29 |
| | 4.2.1.7 | R_VOCA_VideoOutputCheckEnable | 31 |
| | 4.2.1.8 | R_VOCA_VideoOutputCheckDisable | 33 |
| | 4.2.1.9 | R_VOCA_StatusGet | 35 |
| | 4.2.1.10 | R_VOCA_StatusClear | 37 |
| | 4.2.1.11 | R_VOCA_MonitorAreaSet | 39 |
| | 4.2.1.12 | R_VOCA_ColorRamSet | 41 |
| | | | |



Renesas Graphics Library Video Output Checker A (VOCA) Driver

| 4 | .2.1.13 | R_VOCA_VersionStringGet | 43 |
|-----------|----------|-------------------------|----|
| 4 | .2.1.14 | R_VOCA_MacroVersionGet | |
| 4.2.2 | Interru | pt functions | |
| 4 | .2.2.1 | R_VOCA_IntEnable | |
| 4 | .2.2.2 | R_VOCA_IntDisable | |
| 5. Types. | | | 49 |
| 5.1 Bas | ic Types | | 49 |
| 5.2 Def | inition | | 49 |
| 5.2.1 | API Ve | ersion | 49 |
| 5.2.2 | Refere | nce color entry number | 49 |
| 5.3 Enu | | Гуре | |
| 5.3.1 | | Error_t | |
| 5.3.2 | | _MonAreaNum_t | |
| 5.3.3 | | | |
| 5.4 Stru | | e | |
| 5.4.1 | • • | Param_t | |
| 5.4.2 | | MonRefColor_t | |
| 5.4.3 | | MonArea t | |
| 5.4.4 | | AreaStatus_t | |
| | | | |

1.Overview

1.1 Feature and Scope

The VOCA driver checks whether the display content is correctly output by the Video Output. The VOCA driver is only available for the RH850/D1Mx RGL package.

1.2 Component Structure

The component structure of VOCA is shown in *Figure 1-1*.




Figure 1-1 Component Structure

For the details of the API, please refer to *Chapter 4*.

2.Basic Specification

2.1 Summary Specification

The summary of specification is described in *Table 2-1*.

Table 2-1 Summary Specification

| Items | Description | |
|-------------------|---|--|
| Target LSI | RH850/D1M1(H), RH850/D1M1-V2, RH850/D1M1A, RH850/D1M2(H) | |
| | Total of up to 16 monitored areas | |
| | Up to 32,768 pixels in total over all monitored areas | |
| | Four programmable reference color ranges for each monitored area | |
| | Programmable discriminator threshold for fail/pass decision | |
| | Interrupt generation upon | |
| Main Feature | symbol detection mismatch | |
| | - Activity Monitor | |
| | Support both video channels of D1M2(H) and D1M1A devices, that means in particular: | |
| | Total of up to 16 monitored areas on both video output screens supported | |
| | Different number of monitored areas can be assigned to the video outputs | |
| | Activity Monitor supports two separate time windows for the video channels. | |
| Semaphore / Mutex | N/A. This can be implemented with porting layer. | |
| Interrupts | Interrupts can be obtained via ECM. For more details please see section 2.3. | |

2.2 Reserved Word

VOCA uses the following prefixes for avoiding confusion from other software. Prefixes of VOCA is described in *Table*

Table 2-2 Prefixes

| Prefix | Description |
|----------|-------------------------|
| R_VOCA_* | Draffic fan VOOA Madula |
| r_voca_* | Prefix for VOCA Module |

Renesas Graphics Library Video Output Checker A (VOCA) Driver

2.3 Interrupt Handler List

The VOCA interrupts are notified via the Error Control Module (ECM).

The VOCA interrupts are logically OR combined with DISCOM interrupt outputs and input to INTVOCAERR of the ECM.

Table 2-3 Interrupt Handler List

| No. | Interrupt Name | Description |
|-----|----------------|--|
| (1) | INTVOCAERR | Logically OR combination of VOCA and DISCOM error signals. |

Renesas Graphics Library Video Output Checker A (VOCA) Driver

2.4 Error Handling

2.4.1 Return code

VOCA driver has 4 types of error codes.

2.4.1.1 Parameter level

Following errors occur by a cause such as abnormality of parameter. In this case, please set valid parameter again.

- R VOCA ERR PARAM INCORRECT
- R_VOCA_ERR_RANGE_UNIT
- R_VOCA_ERR_RANGE_PARAM

2.4.1.2 Timing level

Following errors occur by a cause such as abnormality of execution timing. In this case, please call again after changing to valid state or timing.

• R VOCA ERR NOT ACCEPTABLE

2.4.1.3 System level

Following errors occur by a cause such as OS dependent error (e.g. system call error, resource shortage). In this case, please do recovery processing from a system layer, because this status cannot be restored only in this library.

• R VOCA ERR FATAL OS

2.4.1.4 Hardware level

Following errors occur when unexpected error occurs internally. In this case, please reset the RH850/D1x device.

• R VOCA ERR FATAL HW

2.5 State Transition

Each VOCA unit has following status.

Table 2-4 VOCA unit State Details

| No. | State Name | Description |
|-----|--|--|
| (1) | Uninitialized Specifies that the VOCA driver is not initialized. | |
| (2) | Initialized | Specifies that the VOCA driver is initialized. |
| (3) | Idle | Specifies that the configuration for Video Output Monitor area or Activity Monitor has been set. |
| (4) | Executing | Specifies that Video Output Monitor or Activity Monitor operation is enabled. |

The image describes state transition.




Figure 2-1 State Transition Diagram of VOCA driver

Renesas Graphics Library Video Output Checker A (VOCA) Driver

Table 2-5 State Transition Table of VOCA unit

| | State | | | |
|--------------------------------|---------------|-------------|------|-----------|
| Function Name | Uninitialized | Initialized | Idle | Executing |
| R_VOCA_Init | ОК | NG | NG | NG |
| R_VOCA_DeInit | ОК | ОК | ОК | NG |
| R_VOCA_ErrorCallbackSet | NG | ОК | ОК | ОК |
| R_VOCA_ParamSet | NG | ОК | ОК | NG |
| R_VOCA_ActiveMonitorEnable | NG | NG | ОК | ОК |
| R_VOCA_ActiveMonitorDisable | NG | ОК | ОК | ОК |
| R_VOCA_VideoOutputCheckEnable | NG | NG | ОК | ОК |
| R_VOCA_VideoOutputCheckDisable | NG | ОК | ОК | ОК |
| R_VOCA_StatusGet | NG | ОК | ОК | ОК |
| R_VOCA_StatusClear | NG | ОК | ОК | ОК |
| R_VOCA_MonitorAreaSet | NG | ОК | ОК | ОК |
| R_VOCA_ColorRamSet | NG | ОК | ОК | ОК |
| R_VOCA_VersionStringGet | OK | ОК | ОК | ОК |
| R_VOCA_MacroVersionGet | OK | ОК | ОК | ОК |
| R_VOCA_IntEnable | NG | ОК | ОК | ОК |
| R_VOCA_IntDisable | NG | ОК | ОК | ОК |

3. Function Description

3.1 Fundamental Concepts

3.1.1 VOCA unit

RH850/D1x device has the following number of units of the VOCA.

Table 3-1 Number of units

| | RH850/D1x Device Name | | |
|--------------|-----------------------|----------------------------------|--|
| Feature | D1L2(H) | D1M1(H), D1M1-V2, D1M1A, D1M2(H) | |
| VOCA Units | 0 | 1 | |
| Unit indexes | None | VOCA0 | |

Almost VOCA API functions have the argument "Unit". User specifies the VOCA H/W unit number to be controlled.

3.1.2 Video channel

RH850/D1x device has the following number of Video channels of the VOCA. Video channel 0 is VDCE Unit 0 output. Video channel 1 is VDCE Unit 1 output.

Table 3-2 Number of Video channels

| | RH850/D1x Device Name | | |
|-----------------------|-----------------------|--------------------------------|--|
| Feature | D1M1(H), D1M1-V2 | D1M1A, D1M2(H) | |
| Video channels | 1 | 2 | |
| Video channel indexes | Video channel0 | Video channel0, Video channel1 | |

3.1.3 Video Output Monitor

RH850/D1x device has up to 16 monitored area of unit of the VOCA.

In the case of D1M1A and D1M2(H), the Video Output Monitor are up to the total 16 monitored areas on both video output screens.

3.1.4 **Video Output Monitoring**

VOCA checks the video output image and the reference image for a rectangle area. The check method is discriminator is calculated, which is a measure of the deviation between the output rectangle and its reference. If the discriminator exceeds a certain threshold the video output is judged as incorrect.

The discriminator calculation is calculated as follows.

Renesas Graphics Library Video Output Checker A (VOCA) Driver

- The video output is performed on reduced 12-bit RGB444 color format instead of 16-/18-/24-bit color.
- The reference image compares against a reference color range (minimum/maximum reference color component) rather than on a particular 12-bit color reference value.
- The discriminator calculation forms an integral value over all pixels of the entire rectangular area.




Figure 3-1 Video Output Monitoring

3.1.5 Discriminator calculation

The discriminator value is a sum of deviations ΔR , ΔG , ΔB of the video output pixel color components from the allowed minimum/maximum reference color component range.

Discriminator = $\Sigma (\Delta R + \Delta G + \Delta B)$

The following figure shows an example how a discriminator is calculated.




Figure 3-2 Deviation calculation example

3.1.6 Monitoring sequence

VOCA monitors only one Video Output Monitor area for one video output frame. If several Video Output Monitor areas are enabled, the monitoring order follows a fixed priority:

priority Video Output Monitor area = 0 > 1 > ... > 15

The time of a content mismatch detection for Video Output Monitor area depends on the total number of monitored areas. Also during switching between the video channels, the detection time of Video Output Monitor area takes one frame for synchronization.

So, the monitoring of Video Output Monitor area recommends to setting Video Output Monitors related to the same video channel consecutively.

e.g. area = 0 to 7 are assigned to Video channel 0, area = 8 to 15 are assigned to Video channel 1.




Figure 3-3 Monitor area priority

Renesas Graphics Library Video Output Checker A (VOCA) Driver

3.1.7 Activity Monitor

The Activity Monitor checks the following conditions. If any of the conditions is not fulfilled the Activity Monitor notifies an error.

- The Video Output Monitor has completed the check of a monitor area before the next VSYNC signal occurs.
- The next VSYNC signal is asserted within a certain time window.

The Activity Monitor works when at least one Video Output Monitor is enabled for the respective Video channel.

3.2 Using the API

3.2.1 Initialization / De-Initialization

_VOCA_Init initializes the driver and the hardware as far as necessary. The Unit parameter holds a number that specifies the VOCA unit number being initialized. This function initializes the Error Callback function. R_VOCA_DeInit function de-initializes the driver and the hardware as far as necessary.

3.2.2 Display Area

The R_VOCA_ParamSet sets the timing information of the horizontal / vertical back porch offset and horizontal / vertical size for a Video channel. The horizontal / vertical back porch offset can be calculated from the parameter of 'Timing' for R_VDCE_DisplayTimingSet function. For detail of 'Timing' parameter, please refer to the 'RH850/D1x Family Renesas Graphics Library Video Data Controller E (VDCE) Driver' specification.

The horizontal / vertical back porch offset values is depending on the polarity of the Hsync and Vsync signals.

• If Hsync and Vsync signals are active high.

The back porch (HOffset) = H.BlankWidth - H.SyncWidth - H.FrontPorchThe back porch (VOffset) = V.BlankWidth - V.SyncWidth - V.FrontPorch




Figure 3-4 horizontal / vertical back porch offset and horizontal / vertical size for Sync is active high

• If Hsync and Vsync signals are active low.

 $\label{eq:hamiltonian} The \ back \ porch \ (HOffset) = H.BlankWidth - H.FrontPorch$ $The \ back \ porch \ (VOffset) = V.BlankWidth - V.FrontPorch$




Figure 3-5 horizontal / vertical back porch offset and horizontal / vertical size for Sync is active low

3.2.3 Video Output Monitor area

R_VOCA_MonitorAreaSet sets the information of horizontal / vertical start position, size and reference colors for a Video Output Monitor area.




Figure 3-6 Video Output Monitor area

3.2.4 Reference color


The reference colors for the discriminator calculation are stored as 2-bit CLUT2 indices, that select one out of four 12bpp RGB444 colors from a color look-up table.

R_VOCA_ColorRamSet sets the address, size and the color table of the reference colors RAM for Video Output Monitor areas. The total number of monitored pixel is up to 32,768 pixels.

The reference colors RAM and video output monitor area numbers are associated to as follows.

Renesas Graphics Library Video Output Checker A (VOCA) Driver

- The reference RAM address set by R VOCA ColorRamSet is set to RamAddr of r voca MonArea t structure using R VOCA MonitorAreaSet.
- Video Output Monitor area number is set to MonAreaNum of the r voca MonArea t structure.



The reference colors should be placed sequentially from top-left to bottom-down.

bit position **Table** 15-14 13-12 11-10 5-4 3-2 1-0 9-8 7-6 Table[0x000] pixel 0 pixel 1 pixel 2 pixel 3 pixel 4 pixel 5 pixel 6 pixel 7 pixel 10 Table[0x001] pixel 8 pixel 11 pixel 12 pixel 13 pixel 15 pixel 9 pixel 14 pixel 1018 pixel 1020 pixel 1021 Table[0x07F] pixel 1016 pixel 1017 pixel 1019 pixel 1022 pixel 1023

Table 3-3 The reference colors bit position example for R_VOCA_ColorRamSet

3.2.5 The Video Output Monitor Check Enable / Disable

R_VOCA_VideoOutputCheckEnable enables the check of the Video Output Monitor specified. The result of the Video Output Monitor area uses R VOCA StatusGet. R VOCA VideoOutputCheckDisable ends check of the Video Output Monitor specified.

3.2.6 The Activity Monitor Enable / Disable

R_VOCA_ActiveMonitorEnable sets the upper and lower detection time for Activity Monitor for the Video channel specified, and completed the check of the next VSYNC signal occurs, and the next VSYNC signal is asserted within a certain time. The result of the Activity Monitor uses R_VOCA_StatusGet. R_VOCA_ActiveMonitorDisable ends the Activity Monitor.

COM IDENTIAL

3.3 Device difference

The following table shows the function differences depending on the device.

Renesas Graphics Library Video Output Checker A (VOCA) Driver

Table 3-4 APIs supported by VOCA driver

| | RH850/D1x Device Name | |
|------------------------|-----------------------|----------------------------------|
| Feature | D1L2(H) | D1M1(H), D1M1-V2, D1M1A, D1M2(H) |
| All API of VOCA driver | No | Full |

The following table shows units difference depending on the device.

Table 3-5 Number of Video channels

| Tuble 6 5 Tumber of Video chamies | | |
|-----------------------------------|-----------------------|--------------------------------|
| | RH850/D1x Device Name | |
| Feature | D1M1(H), D1M1-V2 | D1M1A, D1M2(H) |
| Video channels | 1 | 2 |
| Video channel indexes | Video channel0 | Video channel0, Video channel1 |

3.4 Header File List

Table 3-6 Header File List

| No. | Header File Name | Description |
|-----|------------------|--|
| (1) | r_voca_api.h | Header file for VOCA API. |
| (2) | r_typedefs.h | Header file for predefined data types. |

4.Functions

4.1 Function List

This section describes about the VOCA API functions which are in *Table 4-1* and executable state of each function is described in the specification of each function.

Table 4-1 List of VOCA API Functions

| Function Name | Purpose |
|--------------------------------|--|
| R_VOCA_Init | This function initializes the driver and the hardware as far as necessary. |
| R_VOCA_Delnit | This function de initializes the driver and the hardware. |
| R_VOCA_ErrorCallbackSet | This function registers for retrieving the notification on an event. |
| R_VOCA_ParamSet | This function sets the information of a Video channel. |
| R_VOCA_ActiveMonitorEnable | This function enables Activity Monitor. |
| R_VOCA_ActiveMonitorDisable | This function disables Activity Monitor. |
| R_VOCA_VideoOutputCheckEnable | This function enables Video Output Monitor check. |
| R_VOCA_VideoOutputCheckDisable | This function disables Video Output Monitor check. |
| R_VOCA_StatusGet | This function gets the result of Video Output Monitor area error and Activity Monitor error. |
| R_VOCA_StatusClear | This function clears the result of Video Output Monitor area error and Activity Monitor error. |
| R_VOCA_MonitorAreaSet | This function sets the information of Video Output Monitor area. |
| R_VOCA_ColorRamSet | This function sets the reference colors. |
| R_VOCA_VersionStringGet | This function returns the version string of this VOCA driver. |
| R_VOCA_MacroVersionGet | This function returns the major and minor version of the H/W macro. |
| R_VOCA_IntEnable | This function enables the specified VOCA interrupt. |
| R_VOCA_IntDisable | This function disables the specified VOCA interrupt. |

Renesas Graphics Library Video Output Checker A (VOCA) Driver

4.2 VOCA API Functions

This chapter describes the application interface functions, which are required for general use of the driver.

4.2.1 Basic functions

The section describes driver functions, which are required for general use of the driver, but which are related to a specific functionality of the macro itself.

4.2.1.1 R_VOCA_Init

Function Prototypes

r_voca_Error_t R_VOCA_Init(const uint32_t Unit)

Input Parameter

Table 4-2 Input parameter of R VOCA Init

| Parameter | Description |
|-----------|---------------------------------|
| Unit | Specifies the VOCA unit number. |

Input-Output Parameter

None

Output Parameter

None

Renesas Graphics Library Video Output Checker A (VOCA) Driver

Return Codes

R_VOCA_ERR_OK - No error occurred.

R_VOCA_ERR_RANGE_UNIT - The unit-number was outside the range.

R_VOCA_ERR_NOT_ACCEPTABLE - A function was called in an incorrect state.

R_VOCA_ERR_FATAL_OS - Fatal error has occurred at OS interface.

R_VOCA_ERR_FATAL_HW - Fatal error has occurred at H/W.

Description

This function initializes the driver and the hardware as far as necessary.

VOCA unit status will become Initialized state after the execution of this function.

This function issues a software reset of VOCA unit. So, wait for occurrence of interrupt INTVDCE0S0LOVSYNC for VDCE0 in order to the VOCA software reset has been completed.

Reentrancy

Non-reentrant

If user implements following functions to prevent multiple executions, this function will become re-entrant.

- R VOCA Sys Lock
- R_VOCA_Sys_Unlock

Sync/Async

Synchronous

Call from Interrupt

Prohibited.

Preconditions

See Table 2-5 about VOCA unit status conditions.

This function must be called after call to R_VDCE_DisplayEnable for VDCE0 function.

See also

r_voca_Error_t

Renesas Graphics Library Video Output Checker A (VOCA) Driver

4.2.1.2 R_VOCA_Delnit

Function Prototypes

r_voca_Error_t R_VOCA_DeInit(const uint32_t Unit)

Input Parameter

Table 4-3 Input parameter of R VOCA DeInit

| | Parameter | Description |
|----|-----------|---------------------------------|
| Uı | nit | Specifies the VOCA unit number. |

Input-Output Parameter

None

Output Parameter

None

Return Codes

R_VOCA_ERR_OK - No error occurred.

R_VOCA_ERR_RANGE_UNIT - The unit-number was outside the range.

R_VOCA_ERR_NOT_ACCEPTABLE - A function was called in an incorrect state.

R_VOCA_ERR_FATAL_OS - Fatal error has occurred at OS interface.

Description

This function de-initializes the driver and the hardware.

VOCA unit status will become Uninitialized state after executing this function.

If VOCA unit is already de-initialized status, this function does nothing and returns R_VOCA_ERR_OK

Renesas Graphics Library Video Output Checker A (VOCA) Driver

Reentrancy

Non-reentrant as default.

If user implements following functions to prevent multiple executions, this function will become re-entrant.

- R_VOCA_Sys_Lock
- R_VOCA_Sys_Unlock

Sync/Async

Synchronous

Call from Interrupt

Prohibited.

Preconditions

See *Table 2-5* about VOCA unit status conditions.

See also

r_voca_Error_t

COM IDENTIAL

4.2.1.3 R_VOCA_ErrorCallbackSet

Renesas Graphics Library Video Output Checker A (VOCA) Driver

Function Prototypes

Input Parameter

Table 4-4 Input parameter of R VOCA ErrorCallbackSet

| Parameter | Description |
|---------------|--|
| Unit | Specifies the VOCA unit number. |
| ErrorCallback | Specifies a function that is called in case an error occurred. Set R NULL if callback is uninstalled. |

Table 4-5 Output parameter of R_VOCA_ErrorCallbackSet

| Parameter | Description |
|-----------|--|
| Unit | VOCA unit number where the error occurred. |
| Error | Error type. |

Input-Output Parameter

None

Output Parameter

None

Return Codes

R_VOCA_ERR_OK - No error occurred.

R_VOCA_ERR_NOT_ACCEPTABLE - A function was called in an incorrect state.

R_VDCE_ERR_FATAL_OS - Fatal error has occurred at OS interface.

Description

This function sets a callback function that is called in case of an error.

Error notified in this callback can be checked also by return value of each API function, so use of callback is not mandatory. The error callback is global for all VOCA units.

The error callback is notified during the VOCA unit is not Uninitialized state.

The installed error callback can be uninstalled by R_NULL setting in this function. And all VOCA units are de-initialized by R_VOCA_DeInit, the callback is also uninstalled.

Renesas Graphics Library Video Output Checker A (VOCA) Driver

Reentrancy

Non-reentrant as default.

If user implements following functions to prevent multiple executions, this function will become re-entrant.

- R_VOCA_Sys_Lock
- R_VOCA_Sys_Unlock

Sync/Async

Synchronous

Call from Interrupt

Prohibited.

Preconditions

See *Table 2-5* about VOCA unit status conditions.

See also

r_voca_Error_t

COMITEINIAL

4.2.1.4 R_VOCA_ParamSet

Function Prototypes

Renesas Graphics Library Video Output Checker A (VOCA) Driver

Input Parameter

Table 4-6 Input parameter of R VOCA ParamSet

| Parameter | Description |
|-----------|---|
| Unit | Specifies the VOCA unit number. |
| VoCh | Specifies the Video channel. |
| Param | Specifies the VOCA configuration parameter information. |

Input-Output Parameter

None

Output Parameter

None

Return Codes

R_VOCA_ERR_OK - No error occurred.

R_VOCA_ERR_RANGE_UNIT - The unit-number was outside the range.
R_VOCA_ERR_RANGE_PARAM - A parameter was outside the range.

R_VOCA_ERR_PARAM_INCORRECT - Parameter was incorrect.

R_VOCA_ERR_NOT_ACCEPTABLE - A function was called in an incorrect state.
R_VOCA_ERR_FATAL_OS - Fatal error has occurred at OS interface.

Description

This function sets the display timing information of horizontal / vertical back porch offset and horizontal / vertical size for a Video channel.

This function returns R_VOCA_ERR_OK if successful.

This setting is valid until R_VOCA_DeInit is executed.

See *Table 3-2* about the range for Video channels.

Reentrancy

Non-reentrant as default.

If user implements following functions to prevent multiple executions, this function will become re-entrant.

- R_VOCA_Sys_Lock
- R VOCA Sys Unlock

Sync/Async

Synchronous

Renesas Graphics Library Video Output Checker A (VOCA) Driver

Call from Interrupt

Prohibited.

Preconditions

See *Table 2-5* about VOCA unit status conditions.

See also

r_voca_Error_t r_voca_VoCh_t r_voca_Param_t

Renesas Graphics Library Video Output Checker A (VOCA) Driver

4.2.1.5 R_VOCA_ActiveMonitorEnable

Function Prototypes

Input Parameter

Table 4-7 Input parameter of R_VOCA_ActiveMonitorEnable

| Parameter | Description |
|-----------|---|
| Unit | Specifies the VOCA unit number. |
| VoCh | Specifies the Video channel. |
| MaxTime | Specifies the upper detection time for Activity Monitor in 0.033 ms units 0: 0 ms 1: 0.033 ms 2: 0.067 ms 3: 0.1 ms 4094: 136.467 ms |
| MinTime | Specifies the lower detection time for Activity Monitor in 0.033 ms units 0: 0 ms 1: 0.033 ms 2: 0.067 ms 3: 0.1 ms 4094: 136.467 ms 4095: 136.5 ms |

Input-Output Parameter

None

Output Parameter

None

Return Codes

R_VOCA_ERR_OK
- No error occurred.

R_VOCA_ERR_RANGE_UNIT
- The unit-number was outside the range.
- A parameter was outside the range.
- A parameter was incorrect.
- Parameter was incorrect.
- A function was called in an incorrect state.
- Fatal error has occurred at OS interface.

Renesas Graphics Library Video Output Checker A (VOCA) Driver

Description

This function enables Activity Monitor for the specified Video channel.

MaxTime and MinTime of the parameters set the upper and lower detection time for Activity Monitor for Video channel.

If the function successfully executes, the return code will be $R_VOCA_ERR_OK$.

VOCA unit status will become Executing state after the execution of this function.

This function works when at least one Video Output Monitor is enabled for the respective Video channel.

See *Table 3-2* about the range for Video channels.

Reentrancy

Non-reentrant as default.

If user implements following functions to prevent multiple executions, this function will become re-entrant.

- R VOCA Sys Lock
- R_VOCA_Sys_Unlock

Sync/Async

Synchronous

Call from Interrupt

Prohibited.

Preconditions

See *Table 2-5* about VOCA unit status conditions.

See also

r_voca_Error_t r_voca_VoCh_t

4.2.1.6 R_VOCA_ActiveMonitorDisable

Renesas Graphics Library Video Output Checker A (VOCA) Driver

Function Prototypes

r_voca_Error_t R_VOCA_ActiveMonitorDisable(const uint32_t Unit, const r_voca_VoCh_t VoCh)

Input Parameter

Table 4-8 Input parameter of R VOCA ActiveMonitorDisable

| Parameter | Description |
|-----------|---------------------------------|
| Unit | Specifies the VOCA unit number. |
| VoCh | Specifies the Video channel. |

Input-Output Parameter

None

Output Parameter

None

Return Codes

R_VOCA_ERR_OK - No error occurred.

R_VOCA_ERR_RANGE_UNIT - The unit-number was outside the range.

- Parameter was incorrect R_VOCA_ERR_PARAM_INCORRECT

R_VOCA_ERR_NOT_ACCEPTABLE - A function was called in an incorrect state. R_VOCA_ERR_FATAL_OS

- Fatal error has occurred at OS interface.

Description

This function disables Activity Monitor for the specified Video channel.

If the function successfully executes, the return code will be R_VOCA_ERR_OK.

VOCA unit status will become Idle state if all Video channels has been disabled after the execution of this function.

See *Table 3-2* about the range for Video channels.

Reentrancy

Non-reentrant as default.

If user implements following functions to prevent multiple executions, this function will become re-entrant.

- R VOCA Sys Lock
- R VOCA Sys Unlock

Sync/Async

Synchronous

Call from Interrupt

Prohibited.

Renesas Graphics Library Video Output Checker A (VOCA) Driver

Preconditions

See *Table 2-5* about VOCA unit status conditions.

See also

r_voca_Error_t r_voca_VoCh_t

Renesas Graphics Library Video Output Checker A (VOCA) Driver

4.2.1.7 R_VOCA_VideoOutputCheckEnable

Function Prototypes

r_voca_Error_t R_VOCA_VideoOutputCheckEnable(const uint32_t Unit, const uint32_t MonArea)

Input Parameter

Table 4-9 Input parameter of R_VOCA_VideoOutputCheckEnable

| Parameter | Description | | | | | |
|------------|--|--|--|--|--|--|
| Unit | Specifies the VOCA unit number. | | | | | |
| MonAreaNum | Specifies the Video Output Monitor area number. It can be set multiple flags with OR operation. 0x00000001: Video Output Monitor area 0 0x00000002: Video Output Monitor area 1 0x00000004: Video Output Monitor area 2 0x00000008: Video Output Monitor area 3 0x00000010: Video Output Monitor area 4 0x00000020: Video Output Monitor area 5 0x00000040: Video Output Monitor area 6 0x00000080: Video Output Monitor area 7 0x00000100: Video Output Monitor area 8 0x00000200: Video Output Monitor area 9 0x00000400: Video Output Monitor area 10 0x00000800: Video Output Monitor area 11 0x00001000: Video Output Monitor area 12 0x00002000: Video Output Monitor area 13 0x00004000: Video Output Monitor area 14 0x00008000: Video Output Monitor area 15 | | | | | |

Input-Output Parameter

None

Output Parameter

None

Return Codes

R_VOCA_ERR_OK - No error occurred.

R_VOCA_ERR_RANGE_UNIT - The unit-number was outside the range.

R_VOCA_ERR_PARAM_INCORRECT - Parameter was incorrect

R_VOCA_ERR_NOT_ACCEPTABLE - A function was called in an incorrect state.
R_VOCA_ERR_FATAL_OS - Fatal error has occurred at OS interface.

Description

This function enables monitoring for the specified Video Output Monitor area. If the function successfully executes, the return code will be R_VOCA_ERR_OK. VOCA unit status will become Executing state after the execution of this function.

Renesas Graphics Library Video Output Checker A (VOCA) Driver

Reentrancy

Non-reentrant as default.

If user implements following functions to prevent multiple executions, this function will become re-entrant.

- R_VOCA_Sys_Lock
- R_VOCA_Sys_Unlock

Sync/Async

Synchronous

Call from Interrupt

Prohibited.

Preconditions

See *Table 2-5* about VOCA unit status conditions.

See also

Renesas Graphics Library Video Output Checker A (VOCA) Driver

4.2.1.8 R_VOCA_VideoOutputCheckDisable

Function Prototypes

r_voca_Error_t R_VOCA_VideoOutputCheckDisable(const uint32_t Unit, const uint32_t MonArea)

Input Parameter

Table 4-10 Input parameter of R VOCA VideoOutputCheckDisable

| Parameter | Description | | | | |
|------------|--|--|--|--|--|
| Unit | Specifies the VOCA unit number. | | | | |
| MonAreaNum | Specifies the Video Output Monitor area number. It can be set multiple flags with OR operation. 0x00000001: Video Output Monitor area 0 0x00000002: Video Output Monitor area 1 0x00000004: Video Output Monitor area 2 0x00000008: Video Output Monitor area 3 0x00000010: Video Output Monitor area 4 0x00000020: Video Output Monitor area 5 0x00000040: Video Output Monitor area 6 0x00000080: Video Output Monitor area 7 0x00000100: Video Output Monitor area 8 0x00000200: Video Output Monitor area 9 0x00000400: Video Output Monitor area 10 0x00000800: Video Output Monitor area 11 0x00001000: Video Output Monitor area 12 0x00002000: Video Output Monitor area 13 0x00004000: Video Output Monitor area 14 0x00008000: Video Output Monitor area 15 | | | | |

Input-Output Parameter

None

Output Parameter

None

Return Codes

R_VOCA_ERR_OK - No error occurred.

- The unit-number was outside the range. R_VOCA_ERR_RANGE_UNIT

R_VOCA_ERR_PARAM_INCORRECT - Parameter was incorrect

R_VOCA_ERR_NOT_ACCEPTABLE - A function was called in an incorrect state. R_VOCA_ERR_FATAL_OS - Fatal error has occurred at OS interface.

Description

This function disables monitoring for the specified Video Output Monitor area.

If the function successfully executes, the return code will be R_VOCA_ERR_OK.

VOCA unit status will become Idle state if all Video Output Monitors has been disabled after the execution of this function.

Renesas Graphics Library Video Output Checker A (VOCA) Driver

Reentrancy

Non-reentrant as default.

If user implements following functions to prevent multiple executions, this function will become re-entrant.

- R_VOCA_Sys_Lock
- R_VOCA_Sys_Unlock

Sync/Async

Synchronous

Call from Interrupt

Prohibited.

Preconditions

See *Table 2-5* about VOCA unit status conditions.

See also

4.2.1.9 R_VOCA_StatusGet

Function Prototypes

r_voca_Error_t R_VOCA_StatusGet(const uint32_t Unit, r_voca_AreaStatus_t *const State)

Renesas Graphics Library Video Output Checker A (VOCA) Driver

Input Parameter

Table 4-11 Input parameter of R VOCA StatusGet

| Parameter | Description |
|-----------|---------------------------------|
| Unit | Specifies the VOCA unit number. |

Input-Output Parameter

None

Output Parameter

Table 4-12 Output parameter of R_VOCA_StatusGet

| Parameter | Description |
|-----------|--|
| State | Specified the pointer to the status of Video Output Monitor area error and Activity Monitor error information. |

Return Codes

R_VOCA_ERR_OK - No error occurred.

R_VOCA_ERR_RANGE_UNIT - The unit-number was outside the range.

- Parameter was incorrect. R_VOCA_ERR_PARAM_INCORRECT

R_VOCA_ERR_NOT_ACCEPTABLE - A function was called in an incorrect state. - Fatal error has occurred at OS interface. R_VOCA_ERR_FATAL_OS

Description

This function gets the result of Video Output Monitor area error and Activity Monitor error.

This function gets the number of the current Video Output Monitor area monitored.

Reentrancy

Reentrant.

Sync/Async

Synchronous

Call from Interrupt

Permitted.

Renesas Graphics Library Video Output Checker A (VOCA) Driver

Preconditions

See *Table 2-5* about VOCA unit status conditions.

See also

r_voca_Error_t r_voca_AreaStatus_t

Renesas Graphics Library Video Output Checker A (VOCA) Driver

4.2.1.10 R_VOCA_StatusClear

Function Prototypes

r_voca_Error_t R_VOCA_StatusClear(const uint32_t Unit)

Input Parameter

Table 4-13 Input parameter of R_VOCA_StatusClear

| Parameter | Description |
|-----------|---------------------------------|
| Unit | Specifies the VOCA unit number. |

Input-Output Parameter

None

Output Parameter

None

Return Codes

R_VOCA_ERR_OK - No error occurred.

R_VOCA_ERR_RANGE_UNIT
- The unit-number was outside the range.

R_VOCA_ERR_NOT_ACCEPTABLE
- A function was called in an incorrect state.

R_VOCA_ERR_FATAL_OS
- Fatal error has occurred at OS interface.

R_VOCA_ERR_FATAL_HW
- Fatal error has occurred at H/W.

Description

This function clears the result of Video Output Monitor area error and Activity Monitor error.

This function processes the error interrupt factor of VOCA.

Reentrancy

Non-reentrant.

This function doesn't call R_VOCA_Sys_Lock and R_VOCA_Sys_Unlock.

User should control not to re-enter the same VOCA unit. And user should not execute other functions while this function is being executed.

Sync/Async

Synchronous

Call from Interrupt

Permitted.

Preconditions

See Table 2-5 about VOCA unit status conditions.

Renesas Graphics Library Video Output Checker A (VOCA) Driver

See also

4.2.1.11 R_VOCA_MonitorAreaSet

Renesas Graphics Library Video Output Checker A (VOCA) Driver

Function Prototypes

Input Parameter

Table 4-14 Input parameter of R_VOCA_MonitorAreaSet

| Parameter | Description |
|-----------|--|
| Unit | Specifies the VOCA unit number. |
| VoCh | Specifies the Video channel. |
| MonArea | Specifies the Video Output Monitor area information. |

Input-Output Parameter

None

Output Parameter

None

Return Codes

| R_VOCA_ERR_OK | - No error occurred. |
|----------------------------|--|
| R_VOCA_ERR_RANGE_UNIT | - The unit-number was outside the range. |
| R_VOCA_ERR_RANGE_PARAM | - A parameter was outside the range. |
| R_VOCA_ERR_PARAM_INCORRECT | - Parameter was incorrect. |
| R_VOCA_ERR_NOT_ACCEPTABLE | - A function was called in an incorrect state. |
| R_VOCA_ERR_FATAL_OS | - Fatal error has occurred at OS interface. |
| R VOCA ERR FATAL HW | - Fatal error has occurred at H/W. |

Description

This function sets the information of the start position, the size, the reference RAM start address, the reference color upper and lower limit value for Video Output Monitor area.

If the function successfully executes, the return code will be R_VOCA_ERR_OK.

See *Table 3-2* about the range for Video channels.

Reentrancy

Non-reentrant as default.

If user implements following functions to prevent multiple executions, this function will become re-entrant.

- R_VOCA_Sys_Lock
- R_VOCA_Sys_Unlock

Sync/Async

Synchronous

Renesas Graphics Library Video Output Checker A (VOCA) Driver

Call from Interrupt

Prohibited.

Preconditions

See *Table 2-5* about VOCA unit status conditions.

See also

r_voca_Error_t r_voca_VoCh_t r_voca_MonArea_t

Renesas Graphics Library Video Output Checker A (VOCA) Driver

4.2.1.12 R_VOCA_ColorRamSet

Function Prototypes

Input Parameter

Table 4-15 Input parameter of R VOCA ColorRamSet

| Parameter | Description | |
|-----------|---|--|
| Unit | Specifies the VOCA unit number. | |
| Offset | Specifies the Video Output reference RAM first address. Range is 0 – 4095. | |
| Size | Specifies the Video Output Monitor reference RAM size. Unit is pixel. Range is 1 – 16384. | |
| Table | Specifies the 2-bpp CLUT2 indices of the reference colors. See <i>Table 3-3</i> . | |

Input-Output Parameter

None

Output Parameter

None

Return Codes

R_VOCA_ERR_OK - No error occurred.

R_VOCA_ERR_RANGE_UNIT - The unit-number was outside the range.
R_VOCA_ERR_RANGE_PARAM - A parameter was outside the range.

R_VOCA_ERR_PARAM_INCORRECT - Parameter was incorrect.

R_VOCA_ERR_NOT_ACCEPTABLE - A function was called in an incorrect state.
R_VOCA_ERR_FATAL_OS - Fatal error has occurred at OS interface.

Description

This function sets the reference colors of the 2-bpp CLUT2 indices.

If the function successfully executes, the return code will be R VOCA ERR OK.

The total number of all monitored areas is up to 32,768 pixels.

See 3.2.4 for the detail.

Following equations must be satisfied. Otherwise this function will return error.

· (Offset * 8 + Size) <= 32,768 pixels.

This function sets the reference color in units of 8 pixels. If the Size is not in units of 8 pixels, set the last remainder data and set the fraction to 0.

e.g. Offset = 0x010, Size = 1 pixel, Table sets the reference color.

| Toble | bit position | | | | | | | |
|--------------|--------------|-------|-------|-----|-----|-----|-----|-----|
| Table | 15-14 | 13-12 | 11-10 | 9-8 | 7-6 | 5-4 | 3-2 | 1-0 |
| Table[0x010] | pixel 0 | 0 | 0 | 0 | 0 | 0 | 0 | 0 |

Renesas Graphics Library Video Output Checker A (VOCA) Driver

Reentrancy

Non-reentrant as default.

If user implements following functions to prevent multiple executions, this function will become re-entrant.

- R_VOCA_Sys_Lock
- R_VOCA_Sys_Unlock

Sync/Async

Synchronous

Call from Interrupt

Prohibited.

Preconditions

See *Table 2-5* about VOCA unit status conditions.

See also

4.2.1.13 R_VOCA_VersionStringGet

| Function Prototypes |
|--|
| <pre>const uint8_t *R_VOCA_VersionStringGet(void)</pre> |
| Input Parameter |
| None |
| Input-Output Parameter |
| None |
| Output Parameter |
| None |
| Return Codes |
| Version string. |
| Description |
| This function returns version string of the VOCA driver. |
| Reentrancy |
| Reentrant. |
| Sync/Async |
| Synchronous |
| Call from Interrupt |
| Prohibited. |
| Preconditions |
| See <i>Table 2-5</i> about VOCA unit status conditions. |
| See also |
| None |

4.2.1.14 R_VOCA_MacroVersionGet

Function Prototypes

r_voca_Error_t R_VOCA_MacroVersionGet(uint32_t *const Major, uint32_t *const Minor)

Renesas Graphics Library Video Output Checker A (VOCA) Driver

Input Parameter

None

Input -Output Parameter

None

Output Parameter

Table 4-16 Output parameter of R VOCA MacroVersionGet

| Parameter | Description |
|-----------|--------------------|
| Major | The major version. |
| Minor | The minor version. |

Return Codes

R_VOCA_ERR_OK - No error has occurred.

R_VOCA_ERR_PARAM_INCORRECT - Either parameter Major or parameter Minor was R_NULL

Description

This function returns the major and minor version of the H/W macro.

If a callback function is installed with the R_VOCA_ErrorCallbackSet function, errors is notified to Unit0.

Reentrancy

reentrant.

Sync/Async

Synchronous

Call from Interrupt

Prohibited.

Preconditions

See Table 2-5 about VOCA unit status conditions.

See also

Renesas Graphics Library Video Output Checker A (VOCA) Driver

4.2.2 Interrupt functions

4.2.2.1 R_VOCA_IntEnable

Function Prototypes

r_voca_Error_t R_VOCA_IntEnable(const uint32_t Unit)
Input Parameter

Unit)

Table 4-17 Input parameter of R VOCA IntEnable

| Parameter Description | |
|-----------------------|---------------------------------|
| Unit | Specifies the VOCA unit number. |

Input-Output Parameter

None

Output Parameter

None

Return Codes

R_VOCA_ERR_OK - No error occurred.

R_VOCA_ERR_RANGE_UNIT - The unit-number was outside the range.

R_VOCA_ERR_PARAM_INCORRECT - Parameter was incorrect.

R_VOCA_ERR_NOT_ACCEPTABLE - A function was called in an incorrect state.
R_VOCA_ERR_FATAL_OS - Fatal error has occurred at OS interface.

Description

This function enables VOCA interrupt.

If the function successfully executes, the return code will be R_VOCA_ERR_OK.

Reentrancy

Non-reentrant as default.

If user implements following functions to prevent multiple executions, this function will become re-entrant.

- R_VOCA_Sys_Lock
- R_VOCA_Sys_Unlock.

Sync/Async

Synchronous

Call from Interrupt

Prohibited.

Renesas Graphics Library Video Output Checker A (VOCA) Driver

Preconditions

See *Table 2-5* about VOCA unit status conditions.

See also

Renesas Graphics Library Video Output Checker A (VOCA) Driver

4.2.2.2 R_VOCA_IntDisable

Function Prototypes

r_voca_Error_t R_VOCA_IntDisable(const uint32_t Unit)

Input Parameter

Table 4-18 Input parameter of R VOCA IntDisable

| Parameter | Description |
|-----------|---------------------------------|
| Unit | Specifies the VOCA unit number. |

Input-Output Parameter

None

Output Parameter

None

Return Codes

R VOCA ERR OK - No error occurred.

R_VOCA_ERR_RANGE_UNIT - The unit-number was outside the range.

R_VOCA_ERR_PARAM_INCORRECT - Parameter was incorrect.

R_VOCA_ERR_NOT_ACCEPTABLE - A function was called in an incorrect state.

 $R_VOCA_ERR_FATAL_OS$ - Fatal error has occurred at OS interface.

Description

This function disables VOCA interrupt.

If the function successfully executes, the return code will be R_VOCA_ERR_OK.

Reentrancy

Non-reentrant as default.

If user implements following functions to prevent multiple executions, this function will become re-entrant.

- R_VOCA_Sys_Lock
- R_VOCA_Sys_Unlock.

Sync/Async

Synchronous

Call from Interrupt

Prohibited.

Preconditions

See Table 2-5 about VOCA unit status conditions.

Renesas Graphics Library Video Output Checker A (VOCA) Driver

See also

5.Types

5.1 Basic Types

This section shows the basic types used on this library.

Table 5-1 Basic type

| Types | Definition | | Basic types |
|-----------|----------------------------|-----------|--------------------|
| char_t | typedef char | char_t | signed char |
| int8_t | typedef signed char | int8_t | signed char |
| int16_t | typedef signed short | int16_t | signed short |
| int32_t | typedef signed int | int32_t | signed int |
| int64_t | typedef signed long long | int64_t | signed long long |
| uint8_t | typedef unsigned char | uint8_t | unsigned char |
| uint16_t | typedef unsigned short | uint16_t | unsigned short |
| uint32_t | typedef unsigned int | uint32_t | unsigned int |
| uint64_t | typedef unsigned long long | uint64_t | unsigned long long |
| float32_t | typedef float | float32_t | float |
| float64_t | typedef double | float64_t | double |

5.2 Definition

This section shows the definitions used in VOCA API.

5.2.1 API Version

This constant is the value which shows the version information of the VOCA driver.

Table 5-2 Definition of VOCA API Version

| Name | Description |
|--------------------|--|
| IR VOCA VERSION HI | MSB byte of the version information. It is major version information. This |
| | value is changed with release version. |
| R_VOCA_VERSION_LO | LSB byte of the version information. It is miner version information. This |
| | value is changed with release version. |

5.2.2 Reference color entry number

This constant is the value which shows the number of Video Output Monitor area reference color range.

Table 5-3 Definition of Video Output Monitor area reference color range

| Name | Description |
|---------------------------|--|
| R_VOCA_REFCOLOR_RANGE_NUM | Number of Video Output Monitor area reference color range. |

5.3 Enumerated Type

This section shows the enumerated types used in VOCA API Function.

5.3.1 r_voca_Error_t

Description

VOCA driver error code.

If an error occurs, these enumerations give information about the reason.

Definition

```
typedef enum
{
    R_VOCA_ERR_OK = 0,
    R_VOCA_ERR_PARAM_INCORRECT,
    R_VOCA_ERR_RANGE_UNIT,
    R_VOCA_ERR_RANGE_PARAM,
    R_VOCA_ERR_NOT_ACCEPTABLE,
    R_VOCA_ERR_FATAL_OS,
    R_VOCA_ERR_FATAL_HW,
    R_VOCA_ERR_LAST
} r_voca_Error_t;
```

Table 5-4 Enumerator of r voca Error t

| Name | Description | |
|----------------------------|---|--|
| R_VOCA_ERR_OK | No error occurred. | |
| R_VOCA_ERR_PARAM_INCORRECT | A parameter provided to a function was incorrect. | |
| R_VOCA_ERR_RANGE_UNIT | The unit-number was outside the range. | |
| R_VOCA_ERR_RANGE_PARAM | Parameter is the outside the range. | |
| R_VOCA_ERR_NOT_ACCEPTABLE | A function was called in an incorrect state. | |
| R_VOCA_ERR_FATAL_OS | Fatal error has occurred at OS interface. | |
| R_VOCA_ERR_FATAL_HW | Fatal error has occurred at H/W. | |

See also

5.3.2 r_voca_MonAreaNum_t

Renesas Graphics Library Video Output Checker A (VOCA) Driver

Description

Video Output Monitor areas.

Definition

```
typedef enum {
    R_VOCA_MONITOR_AREA_0
                              = 0,
    R_VOCA_MONITOR_AREA_1,
    R_VOCA_MONITOR_AREA_2,
    R_VOCA_MONITOR_AREA_3,
    R_VOCA_MONITOR_AREA_4,
    R_VOCA_MONITOR_AREA_5,
    R_VOCA_MONITOR_AREA_6,
    R_VOCA_MONITOR_AREA_7,
    R_VOCA_MONITOR_AREA_8,
    R_VOCA_MONITOR_AREA_9,
    R_VOCA_MONITOR_AREA_10,
    R_VOCA_MONITOR_AREA_11,
    R_VOCA_MONITOR_AREA_12,
    R_VOCA_MONITOR_AREA_13,
    R_VOCA_MONITOR_AREA_14,
    R_VOCA_MONITOR_AREA_15,
    R_VOCA_MONITOR_AREA_LAST,
} r_voca_MonAreaNum_t;
```

Table 5-5 Enumerator of r_voca_MonAreaNum_t

| Name | Description |
|------------------------|--------------------------------------|
| R_VOCA_MONITOR_AREA_0 | Video Output Monitor 0 is assigned. |
| R_VOCA_MONITOR_AREA_1 | Video Output Monitor 1 is assigned. |
| R_VOCA_MONITOR_AREA_2 | Video Output Monitor 2 is assigned. |
| R_VOCA_MONITOR_AREA_3 | Video Output Monitor 3 is assigned. |
| R_VOCA_MONITOR_AREA_4 | Video Output Monitor 4 is assigned. |
| R_VOCA_MONITOR_AREA_5 | Video Output Monitor 5 is assigned. |
| R_VOCA_MONITOR_AREA_6 | Video Output Monitor 6 is assigned. |
| R_VOCA_MONITOR_AREA_7 | Video Output Monitor 7 is assigned. |
| R_VOCA_MONITOR_AREA_8 | Video Output Monitor 8 is assigned. |
| R_VOCA_MONITOR_AREA_9 | Video Output Monitor 9 is assigned. |
| R_VOCA_MONITOR_AREA_10 | Video Output Monitor 10 is assigned. |
| R_VOCA_MONITOR_AREA_11 | Video Output Monitor 11 is assigned. |
| R_VOCA_MONITOR_AREA_12 | Video Output Monitor 12 is assigned. |
| R_VOCA_MONITOR_AREA_13 | Video Output Monitor 13 is assigned. |
| R_VOCA_MONITOR_AREA_14 | Video Output Monitor 14 is assigned. |
| R_VOCA_MONITOR_AREA_15 | Video Output Monitor 15 is assigned. |

See also

5.3.3 r_voca_VoCh_t

Description

Video channels. Video channel is different depending on RH850/D1x device. See *Table 3-2*.

Renesas Graphics Library Video Output Checker A (VOCA) Driver

Definition

```
typedef enum {
    R_VOCA_VO_0
                    = 0,
    R_VOCA_VO_1,
    R_VOCA_VO_LAST,
} r_voca_VoCh_t;
```

Table 5-6 Enumerator of r voca VoCh t

| Name | Description |
|-------------|-----------------|
| R_VOCA_VO_0 | Video channel 0 |
| R_VOCA_VO_1 | Video channel 1 |

See also

5.4 Structure Type

This section shows the structure used in VOCA API Function.

5.4.1 r_voca_Param_t

Description

The type describes the VOCA configuration parameter information.

Definition

```
typedef struct
{
    uint16_t HOffset;
    uint16_t VOffset;
    uint16_t HSize;
    uint16_t VSize;
} r_voca_Param_t;
```

Table 5-7 Member of r voca Param t

| Name | Description |
|---------|---|
| HOffset | Horizontal back porch offset of the Video channel Display area. |
| | Range is 1 – 2047. Vertical back porch offset of the Video channel Display area. |
| VOffset | Range is 1 – 2047. |
| HSize | Horizontal size of the Video channel Display area. |
| | Range is 1 – 1280. Vertical size of the Video channel Display area. |
| VSize | Range is 1 – 1024. |

See also

5.4.2 r_voca_MonRefColor_t

Description

The type describes the Video Output Monitor reference color range. Set each component as RGB888 format.

Definition

```
typedef struct
{
    uint8_t RUpper;
    uint8_t GUpper;
    uint8_t BUpper;
    uint8_t RLower;
    uint8_t GLower;
    uint8_t BLower;
} r_voca_MonRefColor_t;
```

Table 5-8 Member of r voca MonRefColor t

| Name | Description | |
|---------|---|--|
| RUpper | Video Output Monitor reference color red upper limit. | |
| | Range is 0 – 255. | |
| Clippor | Video Output Monitor reference color green upper limit. | |
| GUpper | Range is 0 – 255. | |
| Dilppor | Video Output Monitor reference color blue upper limit. | |
| BUpper | Range is 0 – 255. | |
| RLower | Video Output Monitor reference color red lower limit. | |
| RLowel | Range is 0 – 255. | |
| CI swar | Video Output Monitor reference color green lower limit. | |
| GLower | Range is 0 – 255. | |
| BLower | Video Output Monitor reference color blue lower limit. | |
| blower | Range is 0 – 255. | |

See also

5.4.3 r_voca_MonArea_t

Description

The type describes the Video Output Monitor area information.

Definition

```
typedef struct
{
    uint16_t MonAreaNum;
    uint16_t MonHStart;
    uint16_t MonVStart;
    uint16_t MonVSize;
    uint16_t MonVSize;
    uint16_t RamAddr;
    uint32_t Threshold;
    r_voca_MonRefColor_t RefColor[R_VOCA_REFCOLOR_RANGE_NUM];
} r_voca_MonArea_t
```

Table 5-9 Member of r_voca_MonArea_t

| Name | Description |
|------------|---|
| MonAreaNum | Video Output Monitor area number. |
| WonAreanum | Range is 0 – 15. |
| | Video Output Monitor area horizontal start position. |
| | Range is 0 – 1279. |
| MonHStart | Horizontal start position value is pixel. |
| | Horizontal start position value should be smaller than 'HSize'. |
| | 'HSize' is the parameter of R_VOCA_ParamSet function. |
| | Video Output Monitor area vertical start position. |
| | Range is 0 – 1023. |
| MonVStart | Vertical start position value is pixel. |
| | Vertical start position value should be smaller than 'VSize'. |
| | 'VSize' is the parameter of R_VOCA_ParamSet function. |
| | Horizontal size of Video Output Monitor area. |
| | Range is 1 – 128. |
| MonHSize | Horizontal start position value is pixel. |
| | The value should be set as follows: |
| | 'HSize@r_voca_Param_t >= MonHStart+ MonHSize'. |
| | Vertical size of Video Output Monitor area. |
| | Range is 1 – 128. |
| MonVSize | Vertical start position value is pixel. |
| | The value should be set as follows: |
| | 'VSize@r_voca_Param_t >= MonVStart + MonVSize'. |
| RamAddr | Video Output Monitor reference RAM start address. |
| | Range is 0 – 4095. |
| Threshold | Video Output Monitor m acceptance threshold. |
| THESHOL | Range is 1 – 262143. |
| RefColor | Video Output Monitor reference color range. |

See also

 $r_voca_MonRefColor_t$

5.4.4 r_voca_AreaStatus_t

Description

The type describes the status of Video Output Monitor area and Activity Monitor.

Renesas Graphics Library Video Output Checker A (VOCA) Driver

Definition

```
typedef struct {
  uint32_t
                       MonArea;
  uint32_t
                       VoCh;
  r_voca_MonAreaNum_t SelMon;
} r_voca_AreaStatus_t;
```

Table 5-10 Member of r voca AreaStatus t

| Name | Description |
|---------|--|
| MonArea | Video Output Monitor area error information. 0x00000000 : There is no error in Video Output Monitor area 0x00000001 : Video Output Monitor area 0 0x00000002 : Video Output Monitor area 1 0x00000004 : Video Output Monitor area 2 0x00000008 : Video Output Monitor area 3 0x00000010 : Video Output Monitor area 4 0x00000020 : Video Output Monitor area 5 0x00000040 : Video Output Monitor area 6 0x00000080 : Video Output Monitor area 8 0x00000200 : Video Output Monitor area 9 0x00000400 : Video Output Monitor area 10 0x00000800 : Video Output Monitor area 11 0x00001000 : Video Output Monitor area 12 0x00002000 : Video Output Monitor area 13 0x00004000 : Video Output Monitor area 14 0x00008000 : Video Output Monitor area 14 0x00008000 : Video Output Monitor area 15 |
| VoCh | Video Output Channel error information for Activity Monitor. 0x00000000 : There is no error in Video Output channel 0x00000001 : Video Output channel error 0 0x00000002 : Video Output channel error 1 |
| SelMon | The number of the current Video Output Monitor area monitored. |

See also

r_voca_MonAreaNum_t

| Renesas Graphics Library Video Output Checker A (VOCA) Driver |
|--|
| User's Manual: Software |

| Rev. | Date | Description | | | | |
|------|----------------|----------------------------|---|--|--|--|
| | | Page | Summary | | | |
| 0.1 | Oct 11, 2019 | - | First edition. | | | |
| 0.2 | Nov 22, 2019 | 25, 39 | Added the const or the pointer to arguments. | | | |
| | | 21, 27, 29, 31, 33, 39, | | | | |
| | | 55 | Fixed typo. | | | |
| | | 56 | Fixed the value of r_voca_AreaStatus_t. | | | |
| 0.3 | Dec 20, 2019 | 8 | Changed "Executing" State transition for R_VOCA_ParamSet. | | | |
| | | 23 | Added argument. | | | |
| | | 41 | Added the description about the setting if the reference colors are 7 pixels or less. | | | |
| | | 49 | Added R_VOCA_REFCOLOR_RANGE_NUM to Definition. | | | |
| 1.0 | April 24, 2020 | 9-16 | Added traceability ID | | | |

Renesas Graphics Library Video Output Checker A (VOCA) Driver

User's Manual: Software

Publication Date: Rev.0.1 Oct 11, 2019

Rev.1.0 April 24, 2020

Published by: Renesas Electronics Corporation



SALES OFFICES

Renesas Electronics Corporation

http://www.renesas.com

Refer to "http://www.renesas.com/" for the latest and detailed information.

Renesas Electronics Corporation TOYOSU FORESIA, 3-2-24 Toyosu, Koto-ku, Tokyo 135-0061, Japan

Renesas Electronics America Inc. Milpitas Campus 1001 Murphy Ranch Road, Milpitas, CA 95035, U.S.A. Tel: +1-408-432-8888, Fax: +1-408-434-5351

Renesas Electronics America Inc. San Jose Campus 6024 Silver Creek Valley Road, San Jose, CA 95138, USA Tel: +1-408-284-8200, Fax: +1-408-284-2775

Renesas Electronics Canada Limited 9251 Yonge Street, Suite 8309 Richmond Hill, Ontario Canada L4C 9T3 Tel: +1-905-237-2004

Renesas Electronics Europe GmbH Arcadiastrasse 10, 40472 Düsseldorf, Germany Tel: +49-211-6503-0, Fax: +49-211-6503-1327

Renesas Electronics (China) Co., Ltd.
Room 101-T01, Floor 1, Building 7, Yard No. 7, 8th Street, Shangdi, Haidian District, Beijing 100085, China Tel: +86-10-8235-1155, Fax: +86-10-8235-7679

Renesas Electronics (Shanghai) Co., Ltd.
Unit 301, Tower A, Central Towers, 555 Langao Road, Putuo District, Shanghai 200333, China Tel: +86-21-2226-0888, Fax: +86-21-2226-0999

Renesas Electronics Hong Kong Limited
Unit 1601-1611, 16/F., Tower 2, Grand Century Place, 193 Prince Edward Road West, Mongkok, Kowloon, Hong Kong Tel: +852-2265-6688, Fax: +852 2886-9022

Renesas Electronics Taiwan Co., Ltd.
13F, No. 363, Fu Shing North Road, Taipei 10543, Taiwan Tel: +886-2-8175-9600, Fax: +886 2-8175-9670

Renesas Electronics Singapore Pte. Ltd. 80 Bendemeer Road, #06-02 Singapore 339949 Tel: +65-6213-0200, Fax: +65-6213-0300

Renesas Electronics Malaysia Sdn.Bhd.
Unit No 3A-1 Level 3A Tower 8 UOA Business Park, No 1 Jalan Pengaturcara U1/51A, Seksyen U1, 40150 Shah Alam, Selangor, Malaysia Tel: +60-3-5022-1288, Fax: +60-3-5022-1290

Renesas Electronics India Pvt. Ltd.
No.777C, 100 Feet Road, HAL 2nd Stage, Indiranagar, Bangalore 560 038, India Tel: +91-80-67208700

Renesas Electronics Korea Co., Ltd.
17F, KAMCO Yangjae Tower, 262, Gangnam-daero, Gangnam-gu, Seoul, 06265 Korea
Tel: +82-2-558-3737, Fax: +82-2-558-5338



ルネサスエレクトロニクス株式会社

■営業お問合せ窓口

http://www.renesas.com

※営業お問合せ窓口の住所は変更になることがあります。最新情報につきましては、弊社ホームページをご覧ください。

ルネサス エレクトロニクス株式会社 〒135-0061 東京都江東区豊洲3-2-24 (豊洲フォレシア)

| ■技術的なお問合せおよび資料のご請求は下記へどうぞ。 総合お問合せ窓口:https://www.renesas.com/contact/ | | | | | | | | |
|---|--|--|--|--|--|--|--|--|
| | | | | | | | | |
| | | | | | | | | |
| | | | | | | | | |
| | | | | | | | | |
| | | | | | | | | |

Renesas Graphics Library Video Output Checker A (VOCA) Driver

