

HMI Software User Manual

Contents

Chapter 1 Installation	4
1.1 Requirements for installation environment.....	4
1.2 Installation steps	4
Chapter 2 Create simple projects.....	8
2.1 Create a new project.....	8
2.2 Create a new page	8
2.3 Object addition.....	10
2.4 Object editing.....	11
2.5 Simulation	13
2.6 Window cache	14
2.7 Download project files.....	14
2.8 Check the Communication between the Target Board and the PC	16
Chapter 3 Module Functions	18
3.1 System parameter setting	18
3.2 Data sampling.....	19
3.3 Recipe database.....	22
3.4 Operation log settings	26
3.5 Address bar.....	27
3.6 Event login	28
3.7 Device attribute settings	31
3.8 Gallery	35
3.9 User Accounts.....	35
3.10 Timer.....	38
3.11 Action trigger	40
3.12 Multi-language Settings	42
Chapter 4 Common Attributes.....	46
4.1 Overview.....	46
4.2 Attributes.....	46
Chapter 5 Object.....	48
5.1 Lamp.....	48
5.2 Multi-State Lamp.....	49
5.3 Function key	50
5.4 Switch	51
5.5 Multi-State Switch	53
5.6 Slider	55
5.7 Option list.....	57
5.8 Numeric	58
5.9 ASCII	62
5.10 Pie chart.....	64
5.11 Dynamic scale.....	65
5.12 XY plot	67
5.13 Bar graph.....	69
5.14 Meter Display.....	71
5.15 QR code.....	73

5.16 Alarm bar	74
5.17 Time/Date	76
5.18 Input Date/Time	77
5.19 Table	78
5.20 Static/Dynamic Text	79
5.21 Picture	80
5.22 History data view	81
5.23 Recipe view	83
5.24 Operation log view	85
5.25 Alarm view/Event view	87
5.26 Trend chart.....	89
5.27 Horizontal Pipeline/Vertical Pipeline	90
5.28 Pipeline Connector	93
5.29 Vector Graphics	93
5.30 Media Player.....	95
Chapter 6 Others	97
6.1 Input method.....	97
6.2 Download project.....	97
6.3 Register address setting	97
6.4 JavaScript function	98
6.5 Reserved registers.....	108
6.6 Background settings	109
Revision records	110

Chapter 1 Installation

This section explains how to install the HMI software.

1.1 Requirements for installation environment

All the following OS are compatible with the software.

Windows 7 (32bit / 64bit)

Windows 8 (32bit / 64bit)


Windows 8.1 (32bit / 64bit)

Windows 10 (32bit / 64bit)


1.2 Installation steps

- 1) Double click hmi.exe. Select a language and then click **[Next]**.







- 2) Select **[I agree to the terms of this license agreement]**, and click **[Next]**.




- 3) Specify the software installation path. You can use the default path, or you can click **[Change...]** to specify another path, and then click **[Next]**.




- 4) Check **[Install shortcut for current user only]** or **[Make shortcuts available to all users]** and click **[Next]**.



- 5) Click **[Next]** to start the installation.





6) When the installation is complete, click [Finish].



Chapter 2 Create simple projects

2.1 Create a new project


- 1) Open the HMI software and select **[New]**
- 2) Choose suitable model. Click **[Landscape]** or **[Portrait]** to change the direction.
- 3) Click **[Location]** to specify the path to save the new project.
- 4) Click **[OK]** to enter the main interface.



2.2 Create a new page

You can create multiple windows in a project and switch between them.


Select windows and click [+]




Name the window and set the start coordinate, width and height of the window. If not specified, it defaults to the maximum size of the window. Select [Auto center] or not based on your need. Then click [OK].

Note:

- 1) The first window whose id starts with '000' will not be displayed in the current version. Please edit windows from window 001.
- 2) In the current version, it is recommended to set a background picture for every window using a picture that fits the window size. For example, the size of the current window is set to 600×800. So you need to set a background picture using a 600×800 picture. For details, refer to [6.6](#).




As shown in the following figure, you can create multiple windows by following steps above.




2.3 Object addition

Double-click to select the window for placing the object → switch menu bar to **[Object]** menu.




The process of adding an object is as shown in the figure below.

Click an object → drag and drop it to a location in the middle window → double-click on the object to place it.




Place multiple objects.



2.4 Object editing


2.4.1 Paste/Copy/Cut/Delete

Click to select an object. Click **[Copy]** or **[Cut]** to copy the object to clipboard. Click **[Paste]** to paste the object to the window. Press **[Delete]** to delete the object.




2.4.2 Undo/Redo


Click the toolbar. Select **[Undo]** and **[Redo]**.



Click **[Undo]** or press **[Ctrl +Z]** to reserve your last action. Click **[Redo]** or press **[Ctrl +Y]** to reserve a previous Undo. Only Undo and Redo of the currently opened page are supported.




Note: Please click the [save] button at the bottom of [Windows] after Copy/Cut, Paste, Redo and Undo.









2.4.3 Arrange

Select an object. Hold down the **[Ctrl]** key to select multiple objects. Switch menu bar to **[Home]** menu. Click arrangement buttons to arrange objects.






There are five types of arrangements.



1) Align with the datum object (the datum object: the last selected object, that is, the object with small red squares at the four corners).

	Align left with the baseline of the left border of the datum object
	Align vertical center with the vertical center of the datum object
	Align right with the baseline of the right border of the datum object
	Align top with the baseline of the top of the datum object
	Align horizontal center with the baseline of the horizontal center of the datum object
	Align bottom with the baseline of the bottom of the datum object



2) Make same width/height with the datum object (the datum object: selected object with small red squares at the four corners).

	Same width with the datum object
	Same height with the datum object
	Same size (width and height) with the datum object



3) Align with the window

	Vertical center in the window
	Horizontal center in the window

4) Adjust position


	Adjust the position of the selected object. Move 1 pixel at a time. Click the button or use the arrow keys to adjust the position of the selected object.
	Adjust the width and height of the select object. 1 pixel at a time. Click the button or press [Ctrl + arrow keys] (left arrow to decrease and right arrow to increase) to adjust the size.

5) Equally spaced

	Distribute selected objects horizontally
	Distribute selected objects vertically

2.5 Simulation

You can simulation the project operation on PC. Click [Project]->[Simulation]. The simulation function only supports preset JavaScript commands such as switching interface, opening window, etc. For details, refer to [6.4](#).




2.6 Window cache

For a window with many objects, you can right-click on the window and select **[Enable Window Cache]** in the pop-up menu. When switching to the window on the target board, the loading speed can be improved.

2.7 Download project files

1) Download project files via USB flash drive.

Click [Project] -> [Compile]



After the compilation is completed, copy the project file to the USB disk and change the name to update.dpro. Then insert the USB flash drive into the device and power on again, and wait for the device to automatically download the update. (Not available in the current version)



2) Download project files via Ethernet cable

Connect the target board to the PC with an Ethernet cable. Click [Project] -> [Download]. Set the IP address and port of the target board in the pop-up window.

The default IP address is 192.168.10.202 or 192.168.10.201 and the default com is 1502.

Click [OK] and the downloading starts.

Note: Please keep the Ethernet cable connected to your computer and power on the device during downloading.




When the HMI software reminds that the downloading is completed, wait for the device to restart automatically. The device will run the downloaded project after the restart.

You can also shut down the device manually after the downloading is completed and power on again. The device will automatically run the downloaded project after startup.


Note: To achieve communication, the IP addresses of the device and the computer should be in the same network segment during downloading.

You can configure the IP address of the computer as follows.

(1) Open **control panel** and click on “**Network and Internet**” and then click on “**Network and Sharing Center**”. Click on “**Change adapter settings**”.




(2) Right-click on the adapter and select “**Properties**”.




(3) Double-click on “**Internet Protocol Version 4(TCP/IPv4)**”.

(4) Select “**Use the following IP address**” and specify the IP address. The first three numbers should be 192.168.10 to make sure that the computer is in the same network segment with the device. The last number can be filled in 0~255. Do not set it to the same as the IP address of the device. Click the OK button on “Internet Protocol Version 4 (TCP/IPv4) Properties” window, and also click the OK button on “Ethernet Properties” window.




Note: Your computer cannot connect to internet through a cable after changing the IP address to STATIC. You can set your computer back to DHCP to connect to internet. Repeat steps (1)-(3) again. When you get to the “Internet Protocol Version 4 (TCP/IPv4) Properties” window, click “**Obtain an IP address automatically**”.




2.8 Check the Communication between the Target Board and the PC

(1) Click [Project] -> [Device Detection]. Specify the IP address and com in the pop-up window (192.168.10.220 here). Then click [OK].



(2) Click **[Detect]** button of the buzzer. If you hear the beeping sound from the target board, it means that the HMI software and the target board have established a good connection and can communicate normally, otherwise the connection has not been established.



Chapter 3 Module Functions

3.1 System parameter setting

This section describes how to configure the system parameter settings.



1 Overview

System parameter settings allow adding, setting, and deleting devices in the HMI device list. The PLC to communicate with the device need to be added here.

2 Settings

Click [**Home**] in the menu bar →click [**System Parameters**] to bring up the [system parameter settings] dialog box.

There is a device named Local HMI by default. Click [**Model**] to modify the local device's parameters such as HMI model and orientation. Restart the project after modifying to ensure normal display.




(1) In the [**device**] page, select a device and click [**delete**] to delete the selected device. The first device in the list is a local device that cannot be deleted.

(2) In the [**device**] page, click [**New**] to bring up the [**Device attributes**] dialog box, the usage of which is explained in [3.7](#).

(3) In the [**Model**] page, you can check and modify the information about this device.

Note: After changing the resolution or orientation, please close and reopen the project immediately.



3.2 Data sampling


This section describes the configuration of data sampling.


1 Overview

The **[data sampling]** module is used to define how the data is sampled, e.g., sampling time and sampling address. The acquired sampling data can be stored at a specified address, e.g., a SD card or a USB flash drive. **[data sampling]** can be used with the [History data view] to view data sampling records.


2 Settings

(1) Click **[Sampling/Data]** in the menu bar → click **[Data Sampling]** in the toolbar to bring up the **[Data Sampling]** window. You can add data or delete and set selected data by the buttons in the lower-left of the window. When deleting and setting, you need to select the data in the list before you can operate.





(2) Click **[New]** or **[Modify]** to bring up the following dialog box, through which new data sampling information can be added. You can also select existing data sampling information and click **[Modify]** to modify it.



Data source
Description:
Device: LOCAL_HMI
Address: IB
☐ Lable

Data record
Max records: 10
Auto stop: ☐
No. of channels: 1

Clear address
☐ Enable
Device: LOCAL_HMI
Address: IB
☐ Lable


History file
Save to: Do not save
Custom path:
Max days to keep: 7

Pause address
☐ Enable
Device: LOCAL_HMI
Address: IB
☐ Lable

Sample mode
Priority: 0
Sampling Mode: Periodic
Period(ms):

OK Cancel

(3) The address of the data source for data sampling can be set and a text description of the data sampling can be made to differentiate between different data samples through **[Data source]**.



Data source


Description:

Device:

Address:

☐ Lable

(4) When **[Clear address]** and **[Pause address]** in the **[Data Sampling]** window are enabled, the address can be configured, and the corresponding functions are enabled. (Not available in the current version)



Clear address

☐ Enable

Device:

Address:

☐ Lable

Pause address


☐ Enable

Device:

Address:

☐ Lable

(5) You can set the maximum sampling number on the immediate mode (That is, if it is not saved to the history record, the maximum number of samples saved in real time), whether to stop automatically (Not available in the current version), and the number of channels (When **[Data source]** is set to IS or QS, the number of channels should be greater than the length of the string that may appear.) in **[Data Record]**.



Data record

Max records:

Auto stop: ☐

No. of channels:

(6) In **[History file]**, you can select **[Save to SD card]**, **[Save to USB]**, **[Custom path]** or **[Do not save]**. If you select **[Save to SD card]** or **[Save to USB]**, it is necessary to edit **[max days to keep]**. The default save path of a USB flash drive is hmi folder in its root directory. If you select **[Save to SD card]**, please check whether a SD card is inserted into the device. Do not add / at the end of the custom path.

History file

Save to: Do not save

Custom path:

Max days to keep: 7

(7) In **[Sample model]**, you can edit the priority as either **[Periodic]** or **[Trigger]**. If **[Periodic]** is selected, the sampling period needs to be set. Otherwise, the trigger address and trigger mode need to be set.

Note: the unit of sampling period is MS. If you want to set to sample every 10s, the sampling period can be set to 10000.

Sample mode

Priority: 0

Sampling Mode: Periodic

Period(ms):

3.3 Recipe database


This section describes how to use the recipe database.


1 Overview

A recipe database is a database defined by the user in the PC configuration software, where certain recorded data can be preset on the PC, or added, deleted and modified on the HMI device. These database files can be downloaded to the device to change and customize the working parameters of the production line.



2 Create a new recipe database

(1) Click **[Sampling/Data]** in the menu bar →click **[Recipe Database]** in the toolbar to bring up the following window.







(2) Create a recipe database: click the button as shown, set [Database Name] in the pop-up window, and click [OK]. Then a recipe database is created.




(3) Add [Item] to the database: click [New] and set [Item name], [Data type] and [Size] in the pop-up window.




And then click [OK], the new item is added.

More items can be added in the same way.

(4) Add data: click [Data] to switch to the following interface and click [New] to add data to the database.



(5) Modify a table: double-click the data, and then you can change it at will.



(6) Click [**Save**] to save the database. When the project is downloaded to the device, the database file will also be downloaded.



(7) Register: You can operate the recipe database in the device through corresponding system register.

Recipe Database	
Definition	Data
1.Db: LOCAL_HMI IW8300	Specify the recipe database currently in operation, the number starts from 0.
2.Selection: LOCAL_HMI IW8301	Current selection of record, the number starts from 0. When the value of Selection changes, the corresponding values will be updated
3.Command: LOCAL_HMI IW8302	Enter a specific numerical command to operate the current recipe database. Enter "1": add a recipe record Enter "2": save the modification of the current recipe record Enter "3": delete the selected recipe record Enter "4": delete all recipe records
4.Result: LOCAL_HMI IW8302	View the result of the command Display "10": the command was executed successfully Display "11": the selected record does not exist Display "12": unknown command Display "13": the record has reached the upper limit (10,000), and new records cannot be added Display "14": other commands are being executed
5.Count: LOCAL_HMI IW8303	Show the number of records in current recipe.
* Maximum 64 databases are supported, and each databases supports a maximum of 1024 fields.	

(8) Import recipe database into the device

You can follow the steps below to import the recipe database into the device via a USB flash drive.

- Edit the recipe database and save it in the HMI software for PC. Export the recipe database to the hmi directory of a USB flash drive.
- Insert the USB flash drive into the device.
- Execute the corresponding script function through the interface button set by yourself. You can refer to the following script function.

```
function importRdb()
{
    var ret = Hmiregs.ImportRdbData(0); // Import the first recipe
}
```

The function description is as follows.

ImportRdbData(recipe database id)

Function description: Import the selected recipe in the hmi directory of the root directory of the USB flash drive into the touch screen.

Parameter description: id of the recipe to be imported. Start from 0 (Number before the name of the recipe-1)

Return:

- 0: Import successfully
- 1: The file to be imported do not exist. / No USB flash drive is inserted.
- 2: The import failed. The imported recipe may not be the recipe file of the current project, or the recipe field has been changed, which does not match the original recipe.
- 3: The recipe does not exist in the device and cannot be imported and replaced.

Precautions:

The imported recipe needs to be placed in the hmi directory of the root directory of the USB flash drive; the imported recipe needs to be the recipe of the same project, and the items of the recipe have not changed. If the project name is different or the recipe items has been re-modified, import will be affected

(9) Export recipes from the touch screen.

You can follow the steps below to export the recipe database into a USB flash drive from the device.

a) Insert the USB flash drive into the device.

b) Execute the corresponding script function through the interface button set by yourself. You can refer to the following script function.

function exportRdb()

```
{
    var ret = Hmiregs.ExportRdbData(0); //Export the first recipe
}
```

The function description is as follows.

ExportRdbData(recipe database id)

Function description: Export the selected recipe to the hmi directory of the root directory of the USB flash drive.

Parameter description: id of the recipe to be exported. Start from 0 (Number before the name of the recipe-1)

Return:

0: Export successfully

-1: No USB flash drive is inserted.

-2: The recipe does not exist.

Precautions:

The exported recipe is placed in the hmi directory of the root directory of the USB flash drive by default;

3.4 Operation log settings


This section explains how to use the operation log setting.


1 Overview

Operation logs can be used to record user's operations. Relevant parameters can be set in [operation log settings].

2 Settings

(1) Click [data/history]→ click [operation log settings] to bring up the window as below.





(2) The following content can be set in the pop-up window.

- Maximum number of logs
- Whether to save to external storage synchronously
- Control address: [log users' operation] can be activated by this address.

3.5 Address bar


This section discusses the functions of the address bar.

1 Overview

The address bar can indicate and retrieve the use of register addresses to allocate address appropriately. (Not available in the current version)

2 Interface description

As below, the address bar is on the left of the software and can be displayed after the [Address bar] item is selected. The address bar is divided into two parts. The upper part is the address retrieval part, and the lower part is the display part.



In the upper part, the address index is switched by selecting devices and addresses, and the lower part presents the address space in the form of squares. Each [green square] represents the corresponding address that is not used and each [red square] indicates the corresponding used address.

3.6 Event login


This section introduces the functions of event login.

1 Overview

[Event login] allows you to view the information of currently alarm events and to add, delete, and modify them.


2 Settings

Click [Sampling/Data] → click [Event log] to pop up as follows.



Select an event. Click [Delete] to delete it. Click [Modify] to modify it. Click [New] to set a new event. The interface to set the alarm event is as follows.

400 018 9008



The image shows a software window titled "Event Log" with a "Statistics" tab selected. The window is divided into several sections for configuring alarm statistics:

- General:** Includes fields for "Basic Buzzer" (with an "Enable" checkbox), "e-Mail", "Confirmed value", and "Message".
- Alarm count statistics address:** Contains a "Device" dropdown menu (set to "LOCAL_HMI"), an "Address" dropdown menu (set to "IB"), and a "Lable" checkbox.
- Alarm time statistics address:** Similar to the count section, with "Device" (LOCAL_HMI), "Address" (IB), and a "Lable" checkbox.
- Save to history:** A section with a "Save to history" checkbox.

At the bottom right, there are "OK" and "Cancel" buttons.

The alarm events can be defined and modified in the above interface.

Event type	Alarm events can be categorized and managed from 0 to 255.
Priority	The priority level of the event.
Read address	The system will read the value of the register corresponding to this address to determine whether the conditions for triggering the event are met.
Notification address	<p>The system will send to the notification address an ON or OFF signal according to the check box when the event occurs.</p> <p>When [Auto reset] is checked, the notification address will return to its original state after the alarm is disarmed.</p>
Condition	<p>When the [Read address] corresponds to a bit register, the [trigger condition] can be set as OFF, ON, ON->OFF, or OFF->ON;</p> <p>The system will monitor the ON/OFF status of the specified bit register to determine whether the trigger condition is satisfied.</p> <p>When the register corresponding to [read address] is not a bit register, the [trigger condition] can be set as ==, >, <, or <>.</p> <p>The system will monitor whether the value of the specified register is equal to, greater than, or less than a specific value.</p> <p>When [reference address] is checked, the trigger condition will refer to the value in the register corresponding to the reference address.</p>
In tolerance	<p>The error allowed when [Condition] is detected.</p> <p>It is valid when the trigger condition is == or < >.</p> <p>For example, if x is the value in the register corresponding to [Read address], the trigger condition is x== 20 and the [in tolerance] is 0.1, the alarm will be triggered only when 19.9 <= x <= 20.1 is satisfied.</p>

When the trigger condition is $x < 20$ and the trigger error is 0.1, the alarm will be triggered when $x < 19.9$ or $x > 20.1$ is met.

Out tolerance	The tolerance allowed when a disarm event is detected, similar to the in tolerance (in tolerance and out tolerance are set independently and do not affect each other).
Delay time for event monitoring when HMI resets	The time for the delay before the value of the specified register is read to determine whether the trigger condition is met after an event is triggered, and the event will not be triggered continuously to cause an alarm.
Buzzer	To enable or disable the buzzer after an event is triggered.
E-mail	The specified addresses to which emails are sent when alarms are triggered or disarmed.
Confirmed value	When an event in the [alarm display] and [event display] objects is acknowledged, this value is written to the [acknowledgment address] specified by the objects. (not available since there is no acknowledgment address in the current version)
Message	The prompt message is displayed in [alarm bar], [alarm view] and [event view] when an event is triggered.
Alarm time statistics register	The time (in seconds) between the event being triggered and being disarmed is written into the register referred to by this address.
Alarm count statistics address	The number of events that have occurred since power on is written into the register indicated by this address.
Save to history	When this tab is checked, the triggered event will be saved as historical data.

3.7 Device attribute settings


This section describes how to set the device related attributes.

1 Overview


In [Device] interface, information of the device to be connected can be set, such as the HMI station number, the name of the device connected to HMI, the interface type, port and station number, etc.

2 Settings

Click [Home] in the menu bar → click [System Parameters] in the toolbar to bring up the [System Parameters Setting] dialog box.




- There is an item in the [Device] dialog by default, which is the local HMI device. Click [Model] if you want to modify attributes of the local HMI device. After changing the resolution or orientation, please close and reopen the project immediately.
- Click [New] in this dialog box to bring up a dialog box, where you can add other devices that you want to connect and set the corresponding device information.



New device information can be set by referring to the following table.

Device Name	The device name is displayed.
Type	<ul style="list-style-type: none"> HMI

HMI Station No.: You can set the station number of HMI, and generally the default station number is used.




The 'Device Attributes' dialog box shows the following configuration:

- Device name: FX3U_32MT
- Type: ☒ HMI, ☐ Device
- HMI Station no.: 0
- Buttons: OK, Cancel

● Device

You can set the information of the added device.



The 'Device Attributes' dialog box shows the following configuration:

- Device name: FX3U_32MT
- Type: ☐ HMI, ☒ Device
- Device Type: fx3u-32mt
- Interface type: PROG_232
- Interface name: COM1
- Station no.: 1
- Buttons: Set, OK, Cancel

Device type

Select the type of connected device from [SIEMENS S300], [SIEMENS S2000] and [fx3u-32mt], etc.

Interface type


Set the interface type to [PROG_232], [MODBUS-TCP] or [MODBUS-RTU].

- When [fx3u-32mt] is selected as the device type, [PROG_232] and [MODBUS-TCP] can be selected as the interface type.
- When [SIEMENS S300] or [SIEMENS S2000] is selected as the device type, [MODBUS-RTU] and [MODBUS-TCP] can be selected as the interface type.

Interface name

Set the communication port or IP address.

- When [MODBUS-RTU] or [PROG_232] is selected as the interface type, click [Set] to open the [communication Port Settings] dialog window and set the communication parameters as follows.



The dialog box titled "Communication Port Settings" contains the following fields:

- Serial port: COM1
- Baud rate: 115200
- Data bits: 8
- Parity: 5
- Stop bits: 1
- Timeout(s): 1
- Delay(ms): 1
- Retry times: 1

Buttons: OK, Cancel

Timeout

The communication interruption exceeds this value (in seconds).


Delay

The HMI will delay this value (in milliseconds) before sending the next command to the device. This parameter will reduce the communication efficiency between HMI and device. If there is no special need, you can set it to "0".

Retry times

The number of commands sent by HMI to the device

- When [MODBUS-TCP] is selected as the interface type, click [set] to open the [IP address setting] dialog window and set the IP address and port number as follows.



The dialog box titled "Communication Port Settings" contains the following fields:

- IP: 0 . 0 . 0 . 0
- Port: 8000
- Timeout(s): 1
- Delay(ms): 1
- Retry times: 1

Buttons: OK, Cancel

Station No.

Sets the default station number. When the specified device address does not include station number information, this value will be used as the station number.

Station no. 1

3.8 Gallery

This section explains how to use the gallery.


1. Overview

[Gallery] is used to display and modify the default images.

2. Interface description

Check the [gallery] bar in the left window to display the gallery.

The gallery bar is divided into two parts. The upper part displays images, and the lower part is for image modification.



Type	To display the images corresponding to the object according to its type.
Index	A object corresponds to a set of images, which are arranged by numbers.
Icon num	An image contains several small icons, When the image is modified, set the number of icons.
[Modify] button	<p>You can modify the image corresponding to its number in [image group].</p> <p>(1)Select the image you want to modify→click [modify]→specify the image in the pop-up dialog box.</p> <p>(2)If there is no image corresponding to a position and thus cannot be selected, you can specify the position number by using the [picture group] drop-down box, and then click the [modify] button to modify it.</p>
[Default] button	To restore the modified image to the default image that comes with the system.

3.9 User Accounts




This section describes how to set the user accounts.

1. overview

[User Accounts] can be used to set multiple users and corresponding passwords.

2. Setup

(1) Click [Tool] in the menu bar → [User Accounts]. You can add, modify and delete user accounts.



Security level


Range: 1 to 6. The smaller the value, the higher the security level. Only if the user level is less than or equal to the object level, the object can be operated, otherwise the object will be hidden.

After the user logs in successfully, the security level of the current user will be written into the LOCAL_HMI IW8200 register, and the current user security level can be obtained from this register.

(2) The device side uses the username and password to log in.

It is necessary to enter the username and password to enter some interfaces on the device side, such as the parameter setting interface. You can set it as follows.

Create a login page in the HMI software. The user can set the username and password in this page.



Username: The character object register needs to be set to: local address LOCAL_HMI IS8202

Password: The character object register needs to be set to: local address LOCAL_HMI IS8214

Login:

Create a login page

When logging in, the value of the LOCAL_HMI IW8220 register needs to be set to 2, indicating that the login operation is in process. The internal program will automatically detect the register value and process accordingly.

Return value of the internal program execution:

When logging in, the internal program will automatically obtain the username and password from LOCAL_HMI IS8202 and IS8214 separately, and then compare it with the username and password set in [User Accounts]. After the comparison, the comparison result will be written to the upper eight bits of the register address LOCAL_HMI IW8220. Different values indicate the following meanings:

0: executing;

1: The verification is successful;

2: No permission;

3: No such user;

4: The password is incorrect;

5: Unknown error.

You can refer to the following function to custom JavaScript.

```
function login()
```

```
{
```

Custom JavaScript

```
//Set the value of IW8220 to 2, indicating that the login operation is in process. The internal program will detect it automatically.
```

```
Hmiregs.SetReg(0,2,8220,2);
```

```
Hmiregs.SetReg(0,2,9812,143); //close the login page before entering a new page
```

```

Hmiregs.MSleep(100);           //Delay 100 MS to wait for the internal program
execution

var v = Hmiregs.GetReg(0,2,8220); //Obtain the result of the internal program
execution

v = v >> 8;                     //Obtain the upper eight bits

if(v == 1){                     // The execution result is 1, indicating that the verification is
successful

Hmiregs.OpenPage(16,0);        //Open a page, such as the parameter settings page
}

// When the execution result is other, a pop-up window can prompt an error, such as the
user name does not exist and the password is incorrect.
}

```

To log out the username and password, please refer to the following methods:

```

function logout()
{
//Clear the username and password register
Hmiregs.SetReg(0,10,8202,"");

//Hmiregs.SetReg(0,10,8202,"defaultuse"); // You can also set the default user to
defaultuse after logout.

Hmiregs.SetReg(0,10,8214,"");
}

```

3.10 Timer


This section describes how to set the timer.

1. overview


[Timer] can be used to set timers.

2. Setup


Click [Object] in the menu bar → [Time-related] → [Timer].



The following window will pop up. You can set some basic attributes of the timer in this window.



Click [New] to add a new timer and the following window will pop up.



The description of these attributes is as follows.

Attributes	Description
Timer type	(1) Pulse: When the input register turns on, timing begins and the output register turns on. After the timing starts, it cannot be stopped until the timing ends, after which the output register turns off.
	(2) On delay: When the input register turns on, timing begins and the output register turns off. During the timing process, if the input register turns off, the elapsed time will be cleared and the timing will stop. After the timing is over, the output register will turn on. Whenever the input register turns on, the output register will turn off.

(3) Off delay: When the input register turns off, timing begins and the output register turns on. During the timing process, if the input register turns on, the elapsed time will be cleared and the timing will stop. After the timing is over, input register will turn on. Whenever the input register turns on, the output register turns on.

(4) Accumulated on delay: When the input register turns on, timing begins. During the timing process, if the input register turns off, the timing will stop but the elapsed time will not be cleared and next timing will start from the kept value. After the timing is over, input register will turn on. Whenever the input register turns off, the output register turns off. The elapsed time will be cleared when the clear control register turns on.

(5) Accumulated off delay: When the input register turns off, timing begins. During the timing process, if the input register turns on, the timing will stop but the elapsed time will not be cleared and next timing will start from the kept value. After the timing is over, input register will turn off. Whenever the input register turns on, the output register turns on. The elapsed time will be cleared when the clear control register turns on.

(6) Timing: When the input register turns on, timing begins and the kept elapsed time will be cleared. When the count reaches the preset time, the elapsed time will be cleared and the timing begins again. The timing will stop only when the input register turns off.

Time interval (MS)	The time interval of each count, in MS.
Input register	Trigger timer
Output register	Set the register when the timing stops.
Measurement register	Set the register to 1 when the timing begins.
Counter register	Save times of timing.
Clear control register	Valid only in accumulated mode. Clear the times of timing when this register turns on.

3.11 Action trigger


This section describes how to use [Action trigger].

1. overview


[Action trigger] can be used to set trigger function. For example, execute corresponding function when the state of some register changes or at set intervals.

2. Setup


Click [Object] in the menu → [Action-related] → [Action trigger].




The following window will pop up. This window is used to display some basic attributes of defined action trigger.



Click [New] to add an action trigger. The following window will pop up.





The dialog box titled "Action Trigger" contains the following fields:

- Description: A text input field.
- Type: A dropdown menu with "Timing trigger" selected.
- Interval(ms): A text input field.
- Branch action: A text input field.

At the bottom right, there are "OK" and "Cancel" buttons.

The description of these attributes is as follows.

Attributes	Description
Type	Address trigger: when the trigger address meets the trigger condition, a branch action will be executed
	Timing trigger: execute a branch action every time interval
Address	When the type is address trigger, the branch action will be executed when the specified register satisfies the trigger condition.
No. of branches	When the type is address trigger, the total number of branch actions corresponding to the trigger address.
Branch action	The action to execute when the branch trigger condition is met. For example, the branch action is filled with a JavaScript function, and the script will be executed when the trigger condition is met.
Condition	When setting the trigger condition, the value should be set to an integer.
	The trigger type is address trigger, the trigger condition is satisfied when the value in the trigger address changes and is equal to the trigger condition
Interval	The timing interval when the type is timing trigger. The unit is milliseconds.


3.12 Multi-language Settings

1. overview


Realize the multi-language switching function on the device side.

2. Setup





Click **[Project]** in the menu → **[String]**




The following window will pop up.



The description of these settings is as follows.

Attributes	Description
	Add a language.
	Delete the selected language. Language001 is the default language and cannot be deleted.
	Export the selected language as .xml file. You can use related software such as Notepad++, Notepad, vscode, UltraEdit to open it. Please retain the original format when translating fields. Do not delete the entire field like <code><sb0051 value="主 页"/></code> .
	Import the translated language file to the project.

Double-click to modify Select a line and double click. You can modify the current field in the pop-up window.




Switch languages on the device side Switching languages register: local HMI register LOCAL_HMI QW9002
The value of this register will be detected automatically by the system. The system will restart automatically and switch languages when the value changes.
When the value of LOCAL_HMI QW9002 register is 1, the corresponding language is language001;

When the value of LOCAL_HMI QW9002 register is 2, the corresponding language is language002;

...



When the value of LOCAL_HMI QW9002 register is N, the corresponding language is language00N;

Note: When placing controls with text after enabling multi-language function, please reserve enough space for other languages. Otherwise, the text will not be displayed completely, such as the figure below.



3.13 Recipe transfer

Recipe transfer is used to transfer the preset value in the recipe database to specified register. You can relate the field and target address in [Object]→[Data Transfer]→[Recipe Transfer].



The relevant script functions used in recipe transmission are as follows.

1. RecipeSetValueToBind(Recipe Database id, record id)

Function Description: Set the data of the selected record in the recipe database to the target register.

Parameters Description: Recipe Database id: start from 0 (number before the recipe name-1).

Record id: the id of the record in the recipe database. Start from 0 (Number before the name of the recipe-1).
The id of the selected record should be smaller than the maximum record.

Value of return:

0: succeeded

-1: failed

Example:

```
function setData()  
{  
    //set the first record of recipe database2(basic recipe database in the above picture) to the target register  
    Hmiregs.RecipeSetValueToBind(1,0);  
}
```

Note: You can preset multiple records in a recipe database. When set the recipe data to the target address, the record id start from 0.

2. RecipeUpdateFromBind(Recipe Database id, record id)

Function Description: Save or synchronize the data of the target register to the selected record in the recipe database.

Parameters Description: Recipe Database id: start from 0 (number before the recipe name-1).

Record id: the id of the record in the recipe database. Start from 0 (Number before the name of the recipe-1).
The id of the selected record should be smaller than the maximum record.

Value of return:

0: succeeded

-1: failed

Example:

```
function updateData()  
{  
    // Save or synchronize the data of the target register to recipe database2(basic recipe database in the  
    above picture).  
    Hmiregs.RecipeUpdateFromBind(1,0);  
}
```

Note: You can preset multiple records in a recipe database. When saving or synchronizing data to the specified record (id starts from 0), the id of the specified record should be smaller than the maximum record.


Chapter 4 Common Attributes

4.1 Overview

You need to set the attributes for objects before using it. Some attributes are common to all objects, and this section introduces the settings of common attributes.

4.2 Attributes

The common attributes are shown as follows.



X and Y	Set x and y coordinates of the object.
Width and height	Set width and height of the object.
Style	<p>Common style attributes, which are the same as HTML rules, are as follows.</p> <ol style="list-style-type: none"> font-size: set the font size, such as "font-size:21;" font-style: set the font style, common settings are as follows. <ul style="list-style-type: none"> normal (default) inherit italic color: set the font color <ul style="list-style-type: none"> Color settings can usually be defined as follows. <ol style="list-style-type: none"> Hexadecimal - e.g., "#ff0000" color name - e.g., "black", "red", "blue", "yellow" and "green" background: set the background color border: set the style of the border, including width, color and style of the border line. Format of these attributes are as follows. <ul style="list-style-type: none"> Width: solid, dashed or dotted Style: x px (no border if not set or set to 0). Color: #ffffff or black

E.g., set to "border:1px solid black", only one blank space between every attribute,
6. padding: set the inner margin, such as "padding:5;"

Note: when setting the object style, you do not need to set all the above attributes. Just modify the default properties that come with the object.

(Set the attributes with ";" separating the different attributes).

The security level of the object.

When it is set to LOCAL HMI:IB0000 or LOCAL HMI:user0000 00000000, there is no security setting and all users can operate this object.


When it is set to "LOCAL HMI:user+ a number", such as "LOCAL HMI:user1","LOCAL HMI:user2", the smaller the number, the higher the security level. Only if the number of the user's security level is smaller or equal to the number of the object's security level, the object can be operated. Otherwise, it will be hidden.

When it is set to other register, whether the object will be displayed is determined by the number of the register. When it is 0, the object will be hidden. When it is not 0, the object will be displayed. (can be used to check whether the object is displayed.)

When multiple objects are overlapped, set the object display layers to 0, 1, 2, 3... The larger the number, the prior the layer order.

Security

Layer



Chapter 5 Object

5.1 Lamp


1 Overview

The [Lamp] object is used to display the status of the bit register.

2 Attributes


Click [Object] in the menu bar → click [Lamp] to bring up the [Lamp] object. Drag the object to the specified [window] and double-click on the object to place it.

After selecting the object in the [window], you can set relevant attributes in the right window.



(1) General attributes

Text	Text displayed by the object. Used to assist text display.
------	---



Marquee style

Default value is 40001003(hexadecimal). That is, horizontally center-aligned, vertically center-aligned, speed set to 3, and 16 frames per second.

Speed = the width of the object/ the value of the lower 8 bits (The value of the lower 8 bits should be smaller than the width of the object). The bigger the lower 8 bits, the fewer steps it takes to play through a loop of marquee and the faster it runs.

Frame rate: how many frames per second. The bigger the value, the faster it runs. The maximum can be set to 20 (hexadecimal), at this time running 32 steps

	per second (frame).
Blink interval	Adjust the blinking speed of the lamp, the larger the value the slower the blinking.
Output reverse	In case of no inversion, if the value in the register of the object is 1, the lamp blinks. The lamp will not blink if the value is 0. In case of inversion, if the value in the register of the object is 0, then the lamp blinks. The lamp will not blink if the value is 1.
Custom picture	Custom the picture of the lamp. You need to input the number of small icons in customized pictures. Then click the button to select pictures.



For example, the number of small icons is 2 in the right picture.

(2) Address setting

Address	Register address referred to by the lamp.
----------------	---

(3) Shape and other attributes settings are detailed in [Chapter 4](#).

5.2 Multi-State Lamp


1 Overview

The [multi-state Indicator] object is used to display the state of the specified register, and more than three states can be shown.

2 Attributes

Click [object]→click [multi-state indicator] to bring up a [multi-state indicator] object. Drag the object to the specified [window] and double-click on the object to place it.

After selecting the object in the [window], you can set relevant attributes in the right window.



(1) General attributes

Text	Text displayed by the object.
Marquee style	Refer to [Marquee style] in [Lamp].
No. of states	The total number of states of the multi-state lamp.

Custom the picture of the multi-state lamp.
You need to input the number of small icons in customized pictures. Then click the button to select pictures.

Custom picture

Custom picture: 2 



For example, the number of small icons is 2 in the right picture.

(2) Address setting

Address	Register address referred to by the multi-status lamp.
---------	--

(3) Shape and other attributes settings are detailed in [Chapter 4](#).

5.3 Function key

1 Overview

The [function key] object provides functions such as window switching, JavaScript command execution and so forth.

2 Attributes

Click [Object] in the menu bar→ click [function key] to bring up a [function key] object. Drag the object to the specified [window] and double-click on the object to place it.



After selecting the object in the [window], you can set relevant attributes in the right window.

GeneralShapeAddress

Function key value

Text:

Text alignment:


Center

JS command:

Command Type:

None

Function Name:




Trigger on release:

☐

Library picture:

1

Custom picture:

 2 

Hide:

☐ Enable

Operation log:

GeneralShapeAddress

Notify address:

Device:

LOCAL_HMI

Address:

IB

☐ Lable

Notify value:

 0

Disable address:

Device:

LOCAL_HMI

Address:

IB

☐ Lable

(1) General attributes

Function key value	<p>If the address of the object is set to be the same as the notification address, the command corresponding to the function key will be sent to the object to realize some function when the function key is pressed. (mainly used to refresh display in the current version)</p> <p>For example, if the [Function key value] is set to 286, the display of the corresponding object will be refreshed.</p>
Text	Text displayed by the object.
Text alignment	Left aligned/ Center-aligned/ Right aligned
JS command	JS command is detailed in 6.4.
Trigger on release	<p>If not checked, JS instruction is triggered by pressing the function key.</p> <p>If checked, JS instruction is triggered on release.</p>
Library picture	Use the specified image in the system gallery as the displayed icon.
Custom picture	When this attribute is set, the user-defined image is used preferentially as the displayed icon.
Operation log	Descriptive statements logged to operation logs using function key value.

(2) Address setting

Notify address	The register is notified when the function key is pressed.
Notify value	The value set to notify the register.
Disable address	Specify the register used to disable the function key. When the value of the register is greater than 0, the function key will not be disabled. Otherwise, the function key will be disabled.

(3) Shape and other attributes settings are detailed in [Chapter 4](#).

5.4 Switch

1 Overview

[Switch] displays the status of the bit registers and defines a touch area on the window that can be pressed to set the status of the indicated bit register as ON or OFF.

2 Attributes

Click [Object]→click [Switch] to bring up a [Switch] object. Drag the object to the specified [window] and double-click on the object to place it.



After selecting the object in the [window], you can set relevant attributes in the right window.

General
Shape
Address

Switch: ☒ Enable
Switch style:

Toggle

Trigger mode:

On pressed

Value of 'ON' state:

1

Marquee style:

00000000

Library picture:

3

Custom picture:

2

 ...
Current state:

0

Fill color:

FF000000

Display text:
Operation log:
JS command:
Command Type:

None

Function Name: ...

General
Shape
Address

Read/Write address:
Device:

LOCAL_HMI

Address:

IB

☐ Lable

Write use diffrent address:
Device:

LOCAL_HMI

Address:

IB

☐ Lable

Disable address:
Device:

LOCAL_HMI


Address:

IB

☐ Lable

(1) General attributes

Switch	If not enabled, the switch does not change when being pressed. It is only used to display.
Switch Style	<p>a. Toggle When this switch is pressed, the status of the specified register will be reversed. E.g., when the status is ON, it will be displayed as OFF. When the status is OFF, it will be displayed as ON.</p> <p>b. Momentary When this switch is pressed, the state of the specified register will be ON first, and when you release the switch, the state will be OFF.</p> <p>c. Set ON The state of the specified register will be set to ON when this switch is pressed. if the register state is ON, press won't change its state.</p> <p>d. Set OFF The state of the specified register will be set to OFF when this switch is pressed. If the register state is OFF, press won't change its state.</p>
Trigger method	<p>To change the trigger method of changing the display state of the switch.</p> <p>On pressed: change the switch display state when pressed.</p> <p>On released: change the state of the switch display when released.</p> <p>(The momentary switch does not have this attribute. The momentary switch is triggered either by pressing or releasing)</p>

Value of 'ON' state	The output value of the register when the switch is set to ON.
Marquee style	Refer to [Marquee style] in [Lamp].
Library picture	Unspecified: Do not use the picture from the library as the icon (set the number of the small icon first). 1-8: Icons are the system default image
Custom picture	The user selects a custom picture to be used as the icon. (input the number of the small icon first) 
Current state	You can select a state and set the displayed color and text of this state.
Fill color	Set the displayed color when the state of the switch is 0 or 1. (Display takes effect when no image is used.)
Display text	Set the displayed text when the state of the switch is 0 or 1.
Operation log	Descriptive statements logged to operation logs when operating the object.
JS command	JS command is detailed in 6.4.

(2) Address settings

Read/write address	The address referred to by the switch.
Write use different address	If this address is set, that is, when the address is not 0, the object read address and written address is different. The switch state is determined by the value in the register corresponding to [read address] . When the switch state is changed, the value corresponding to the new state is written to [read address] and the register corresponding to [write address] . Generally, [read address] and [write address] are the same address.
Disable address	Specify the register used to disable the function key. When the value of the register is greater than 0, the function key will not be disabled. Otherwise, the function key will be disabled.

(3) Shape and other attributes settings are detailed in [Chapter 4](#).

5.5 Multi-State Switch

1 Overview

The [multi-state switch] can display different states according to data in the register and can define a touch area on the window that can be pressed to change the data in the indicated register.

When the multi-state switch is clicked, the value in the specified register is taken out and added by 1. At the same time, the switch turns to the next state and reset until the set maximum state is reached.

2 Attributes

Click [object]→click [multi-state switch] to bring up a [multi-state switch] object. Drag the object to the specified

[window] and double-click on the object to place it.



After selecting the object in the [window], you can set relevant attributes in the right window.

General
Shape
Address

No. of states: 3
Trigger mode: On pressed
Marquee style: 00000000
Library picture: 1
Custom picture: 2
Current state: 0
Fill color: FF000000
Display text:
Operation mode: Auto
Circle mode:
Operation log:

General
Shape
Address

Read/Write address:
Device: LOCAL_HMI
Address: IB
Lable
Write use diffrent address:
Device: LOCAL_HMI
Address: IB
Lable
Disable address:
Device: LOCAL_HMI
Address: IB
Lable

(1) General attributes

No. of states	Number of multi-state switch states. Range: 3-10.
	If the value is set to 3, a maximum of 3 states can be switched.
	If the value is set to 4, a maximum of 4 states can be switched.
...	
Trigger mode	Change the trigger mode of the switch.
Marquee style	Refer to [Marquee style] in [Lamp].
Library picture	Unspecified: Do not use the picture from the library as the icon (set the number of the small icon first).
	1-8: Icons are the system default image
Custom picture	Custom the picture of the multi-state lamp.
	You need to input the number of small icons in customized pictures. Then click the button to select pictures.
Current state	You can select a state and set the displayed color and text of this state.
Fill color	Set the displayed color when the state of the switch is 0 or 1. (Display takes effect when no image is used.)
Display text	Set the displayed text when the state of the switch is 0 or 1.

Operation mode	Auto: The state displayed by the multi-state switch depends on the data in the specified register and cannot be changed manually.
	Plus: increment function. At each press of the object, the data in the specified register is incremented by 1, but the result of the value increase will not exceed the set [Number of States]. If [Circle mode] is enabled, it will be reverted back to the lowest state 0 after reaching the maximum state.
	Minus: decrement function. At each press of the object will result in the data in the specified register is decreased by 1 until it reaches 0. If [Circle mode] is enabled, it will revert back to the highest state after reaching the minimum state.
Circle mode	Refer to the description in the operation mode .
Operation log	Descriptive statements logged to operation logs when operating the object.
JS command	JS command is detailed in 6.4.

(2) Address setting

Read/write address	The address referred to by the switch.
Write use different address	If this address is set, that is, when the address is not 0, the object read address and written address is different.
	The switch state is determined by the value in the register corresponding to [read address]. When the switch state is changed, the value corresponding to the new state is written to [read address] and the register corresponding to [write address].
	Generally, [read address] and [write address] are the same address.
Disable address	Specify the register used to disable the function key. When the value of the register is greater than 0, the function key will not be disabled. Otherwise, the function key will be disabled.

(3) Shape and other attributes settings are detailed in [Chapter 4](#).

5.6 Slider

1 Overview

The [slider] can bind a register to the slide state and alter the value in the corresponding register by the slider position.

2 Attributes

Click [object]→click [slider] to bring up a [slider] object. Drag the object to the specified [window] and double-click on the object to place it.



After selecting the object in the [window], you can set relevant attributes in the right window.

General
Shape
Address

Lower limit: 0
Higher limit: 100
Minimum scale: 3
Set Notification to 1: ☒ Enable
Sliding value: 0
Direction: Left to right
Slider type: 3
Handle width: 25
Groove transparent: ☒ Disable
Background color: FF0066BB
Groove color: FF000011
Handle color: FFFFAA33
Notify before write: ☐ Enable

General
Shape
Address

Read/Write address:
Device: LOCAL_HMI
Address: IB
☐ Lable
Notification address:
Device: LOCAL_HMI
Address: IB
☐ Lable
Monitoring address:
Device: LOCAL_HMI
Address: IB
☐ Lable
Limit address:
Device: LOCAL_HMI
Address: IB
☐ Lable
Disable address:
Device: LOCAL_HMI
Address: IB
☐ Lable

(1) General and other attributes

Lower limit	The slide switch scale minimum.
Higher limit	The slide switch scale maximum.
Minimum scale	Minimum unit of slider movement.
Set notification to 1	If this attribute is enabled, the notification address is set to 1. Otherwise, the notification address is set to 0.
Sliding value	The sliding mode will be enabled after the sliding value is set, and the sliding value is the size of each slide.
Direction	There are four sliding directions. 1. left to right 2. right to left 3. top to bottom 4. bottom to top
Slider type	This value ranging from 0 to 3 represents four different sliders.
Handle width	Set the width of the slider.
Groove transparent	The default is non-transparent, and the slide track will be transparent after the tab is unchecked.
Background color	Designate background color of the slide switch.
Groove color	Designate color of groove.
Handle color	Designate color of the handle.
Notification advance	After the tab is checked, the value of the slider position will inform the notification address before it is written to the [written address] of the corresponding register.

(2) Address setting

Read/write address	The address register controlled by the slider.
---------------------------	--

Notification address	<p>Notification is enabled when this address is not 0.</p> <p>This address will be notified when the value of the slider position is written to the register corresponding to [read/write address].</p> <p>Whether to notify before or after writing is determined by [notification in advance].</p>
Monitoring address	The current value in the register corresponding to [written address] is displayed in real time.
Limit address	When this address is enabled, the slider's lower limit is determined by the value in the register of this address and the upper limit is determined by the value in the address register adjacent to this address.
Disable address	Specify the register used to disable the slider. When the value of the register is greater than 0, the function key will not be disabled. Otherwise, the function key will be disabled.

(3) Shape other attributes settings are detailed in [Chapter 4](#).

5.7 Option list

1 Overview

Drop down the list, and then the value of the selected project can be written to the specified address.

2 Attributes

Click [object]→click [option list] to bring up a [option list] object. Drag the object to the specified [window] and double-click on the object to place it.

After selecting the object in the [window], you can set relevant attributes in the right window.

General

Shape

Address

Mode:

Text

Source data:

Predefine

No. of items:

1

Current item:

1

Item value:

1

Item display text:

text

Set Notification to 1:

☐

Enable

Maximum chars:

Background color:

0

Write address:

Device:

LOCAL_HMI

Address:

IB

☐

Lable

Notify address:

Device:

LOCAL_HMI

Address:

IB

☐

Lable

Data address(valid when source is item address):

Device:

LOCAL_HMI

Address:

IB

☐

Lable

(1) General attributes

Mode	Text, Drop-down list or list.
Source Data	0: Predefine

1: Item address

No. of items	The total number of items in the list. It is valid only if data source is the predefined value.
Current item	When the data source is predefined data , you can select an item for setting.
Item value	When data source is the predefined data , you can set the predefined data as the value written into [Write address] .
Item display text	When data source is the predefined data, you can set the information which is displayed in the option list.
Set Notification to 1	If this attribute is checked, the notification address is set to 1. Otherwise, it is set to 0.
Maximum chars	Valid when data source is set to 1. Output the maximum length of the string of the item address.
Background color	Background color of the selected option list. (Valid when [Mode] is set to [Text] .)

(2) Address setting

Write address	When the mode is text, the number of the item will be displayed according to the value of the register of the [write address] .
Notify address	Valid when the data source is predefined data. This address will be informed when data changes in the register corresponding to the [write address] .
Data address	Valid when the data source is predefined data. This address is used to store the beginning address of the project data.

(3) Shape and other attributes settings are detailed in [Chapter 4](#).

5.8 Numeric


1 Overview

The **[numeric]** object is used to set or display the value in the specified register.

2 Attributes

Click **[object]**→click **[numeric]** to bring up the **[numeric]** object. Drag the object to the specified **[window]** and double-click on the object to place it.

After selecting the object in the **[window]**, you can set relevant attributes in the right window.



The image shows three screenshots of the HMI software configuration interface. The first screenshot shows the 'Common' tab with settings for 'Allow input', 'Password mode', 'Device low', 'Device high', 'Low limit color', 'High limit color', 'Blink interval(ms)', 'Integer digits', 'Decimal places', 'Library picture', 'Border color', 'Fill color', 'Border width', and 'Display convert'. The second screenshot shows the 'Style' tab with settings for 'JS command', 'Command Type', 'Function Name', 'JS execution time', 'JS cache address', 'Device', 'Address', 'Keyboard type', 'Keyboard pos', 'Text alignment', and 'Disable address'. The third screenshot shows the 'Address' tab with settings for 'Read/Write address', 'Device', 'Address', 'Lower limit address', 'Device', 'Address', and 'Higher limit address'.

(1) General attributes

Allow Input	<p>When the input function is enabled, you can manually enter the value to set the specified register.</p> <p>When not enabled, you cannot enter characters manually, and the input box is only used to display the value in the specified register.</p>
Password mode	<p>When password mode is enabled, the entered characters are displayed with “*”.</p>
Device low	<p>The numeric can be written to the specified register only if it is within the lower and upper limits of the device.</p>
Device high	<p>The color of the entered numeric will be red to prompt the user that the numeric exceeds the range.</p>
Low limit color	<p>If the register value is less than [Device low], the background color of the object will be set as the low limit color.</p>
High limit color	<p>If the register value is greater than [Device high], the background color of the object will be set as the high limit color.</p> <p>Note: When there is a trigger warning register, this register controls whether to display the low and high limit colors. At this time, the upper and lower limits will not trigger the warning color. For details, see the description of this attribute.</p>
Blink interval	<p>When the limit color is displayed, if there is a flashing interval, the displayed value will have a flashing effect.</p> <p>The smaller the value of the blinking interval, the faster the flashing, and the minimum value can be set to 50ms.</p> <p>If this attribute is empty, there will be no blinking effect.</p>
Integer digits	<p>To limit the number of digits displayed before and after the decimal point.</p>
Decimal place	
Library picture	<p>Draw using the specified image.</p> <p>If library picture is set to [unspecified], the object icon will not be drawn using the picture, but by specified border color and fill color.</p>
Border color	<p>Valid when library picture is set to [unspecified]. At this time, draw the object</p>

	border using border color.
Fill color	Valid when library picture is set to [unspecified]. At this time, fill the object will the fill color.
Border width	Set the border width when using border color to draw the border.
Display convert	When displaying the value in the register, you can set the register value to be divided by 10/100/1000 to display, or multiplied by 10/100/1000 to display.

(2) Style

JavaScript	Specify the name of the user-defined JS function.Refer to 6.4 Specify the JS script execution time. a. When opening the window The JS command will be executed automatically when opening a new window(interface). b. Before written. The JS function will be executed before the user inputs value to the register. Function: write conversion. This function is described in the JS cache address . c. When the value changes. When the value in the register changes, the JS command will be executed automatically, and the numeric object will display the return value of the JS function. In case of no return value, the object will not display anything. Function: formatting the value in the display register, such as: 38kW, 39°55'21", 12km, etc. JS command can be written as follows to format the display register value.
JS execution time	function printValue() { var v1,v2; //Read values in the register. v1 = Hmiregs.GetReg(0,2,1); //Formatting(customizable) v2 = v1 + 'kW'; return v2; //The numeric object will display the returned sting. } GetReg function parameters detailed information is as follows. Hmiregs.GetReg(0,2,1); If the cache address is xAABBCCCC then 0-AA 2-BB 1-CCCC. Here [JS cache address]: x00020001 is used.
JS cache address	When using this function, you need to set the [JS execution time] to [before writing] You can read this address in the JS script to get the value entered by the user. Then you can write the converted value into the register to realize the conversion function. Example: function jsConvert() {

```
var value;
//Read the user input value from the cache address.
value = Hmiregs.GetReg(0,9,0x00000001);
//Convert the input value (.customizable).
value = value * 3.14159;
// Write the converted value back to the cache address.
Hmiregs.SetReg(0,9,0x00000001,value);
//The program automatically obtains the converted value to determine.
//Only those within the upper and lower device limits will be written to the
specified registers.
}
```

GetReg function parameters are detailed as follows.

Hmiregs.GetReg(0,9,0x00000001);

0: station No. of the device.

9: type of the register

0x00000001: address of the register

SetReg function parameters are similar to GetReg. The last parameter indicates the value written to the register.

Note:

The register type corresponding to the cache address must be double type so that it can cache data of various types, such as 00090001, 00090005, 00090009, etc. When setting it, you should avoid using the same address elsewhere.

Keyboard type	QWERTY: English letters, special symbols, numbers, etc. Numeric: Numbers only. (Only numbers can be entered in the numeric object)
Keyboard pos	Specify the keyboard pop-up position. Down: below the object. Up: above the object. Left: on the left side of the object. Right: on the right side of the object.
Text alignment	Left aligned, center-aligned and right aligned.
Disable address	When the value of the register is greater than 0, the object will be disabled and cannot be operated.

(3) Address setting

Read/write address	The address of the register to read or write.
Lower limit address	When this attribute is activated, the background color of this object will be set to the [low limit color] if the [lower limit address] is greater than 0. Note: If [Device low] and [Low limit address] both are set, the [Low limit address] controls whether to trigger the [low limit color], otherwise the [device low] will trigger the [Low limit color].
Higher limit address	When this attribute is activated, the background color of this object will be set to the [High limit color] of the [Higher limit address] is greater the 0. Note: If [Device high] and [Higher limit address] both are set, the

[Higher limit address] controls whether to trigger the [High limit color], otherwise the [device high] will trigger the [High limit color].

(4) Shape and other attributes settings are detailed in [Chapter 4](#).


5.9 ASCII

1 Overview

The [ASCII] object can be used to enter or display characters in the specified register.

2 Attributes

Click [Object]→click [ASCII] to bring up the [ASCII] object. Drag the object to the specified [window] and double-click on the object to place it.



After selecting the object in the [page], you can set relevant attributes in the right window.

General
Shape
Address

Allow input: Enable

Keyboard type: QWERTY

Keyboard pos: Down

Text alignment: Center

Password mode: ☐ Enable

Maximum chars: 15

Library picture: 1

Border color: 0

Fill color: 0

Border width: 1

Multiline display: ☐ Enable

Hide: ☐ Enable

General
Shape
Address

Address:

Device: LOCAL_HMI

Address: IB

☐ Lable

Disable address:

Device: LOCAL_HMI

Address: IB

☐ Lable

(1) General attributes

Allow input	[enabled]: you can manually enter the value to set the specified register.
	[Disable]: You cannot enter characters manually, and the input box is only used to display the value in the specified register.
	[USB scan code]: After a barcode is scanned by the USB code scanner, the scanned code content can be obtained automatically (in the code scanning mode, characters cannot be manually input, and only one object on a window

can obtain the scanned code content)

Keyboard type	Character keyboard: English letters, special symbols, numbers, etc. Numeric keyboard: Numbers only.
Keyboard pos	Specify the keyboard pop-up position. Below: below the object. Above: above the object. Left: on the left side of the object. Right: on the right side of the object.
Text alignment	Left aligned, center-aligned and right aligned.
Password mode	When password mode is enabled, the entered characters are displayed with “*”.
Maximum chars	Specify the maximum number of characters that can be entered.
Library picture	Draw icons by specified images. If this attribute is set to [Unspecified], the icon is specified by [border color] and [fill color].
Border color	When [Library picture] is set to [Unspecified], you can specify the icon border color.
Fill color	When [Library picture] is set to [Unspecified], you can specify the icon padding color.
Border width	Set the border width when using border color to draw the border.
Multiline display	When enabled, multiple lines can be displayed, and word wrapping is carried out when there is a line feed or when the number of characters exceeds the number of characters in one line. In multi-line display mode, the object is only used to display the characters in the specified register and the input function is not available. (The size of the object should be large enough to display multiple lines.)
Hide	When enabled, the object will be hidden.

(2) Address setting

Address	The register address referred to by the numerical object.
Disable address	Specify the register used to disable the object. When the value of the register is greater than 0, the function key will not be disabled. Otherwise, the function key will be disabled.

(3) Shape and other attributes settings are detailed in [Chapter 4](#).


5.10 Pie chart

1 Overview

The [pie chart] object reads data from multiple channels in succession, starting from the specified address, and displays the proportion of these data by a pie chart.

2 Attributes

Click [object]→click [Chart]→click [pie chart] to bring up the [pie chart] object. Drag the object to the specified [window] and double-click on the object to place it.



After selecting the object in the [window], you can set relevant attributes in the right window.

GeneralShapeAddress

No. of channels:

3

Current channel:

1

Channel fill color:

FF0000

Channel text color:

0000FF

Hole size:

0

Direction:

☐ Counterclockwise

Full circle:

☐ No

Start angle:

0

Stop angle:

360

Border color:

00FFFFFF

Font style:

36

GeneralShapeAddress

Address:

Device:

LOCAL_HMI

Address:

IB

☐ Lable

(1) General attribute

No. of channels	The number of channels displayed in the pie chart, ranging from 2 to 16.
Current channel	You can select certain channel, set parameters i.e., padding color and font color.
Channel fill color	Set the padding color of the selected channel .

Channel text color	Set the font color of the selected channel .
Hole size	The size of the center of the pie chart is within 0 ~ 100 pixels.
Direction	Specify the pie chart direction. Not enabled: Clockwise Enabled: Counterclockwise
Full circle	If checked, the pie chart will not be all-round, and the end angle can be set.
Start angle Stop angle	The start angle can be set from 0 - 360° and the end angle can be set from 0 - 360° (If [full circle] is not checked, only the starting angle works, indicating the position of the 0 scale).
Border color	The border color of the pie chart can be set.
Style and decimals	The data style is specified by two digits. The first digit represents the font style. 1: No data is displayed. 2: The channel data is displayed. 3: The percentage of each channel (the angle number) is displayed. The second digit represents the number of decimal places, which can be set from 1 to 5. Only when the first digit is 2, the input decimals is valid. For instance, “ 24 ” means the channel data is displayed and 4 decimals are reserved.

(2) Address setting

Address	Start address for continuous data acquisition, based on the number of channels
----------------	--

(3) Shape and other attributes settings are detailed in [Chapter 4](#).

5.11 Dynamic scale

1 Overview

The [dynamic scale] object can be in different styles, such as circular, horizontal and vertical scales. The scale content is adjustable to provide scales for other objects such as [bar graph].

2 Attributes

Click [object]→click [chart]→click [dynamic scale] to bring up the [dynamic scale] object. Drag the object to the specified [window] and double-click on the object to place it.



After selecting the object in the [window], you can set relevant attributes in the right window.

Common
Style
Other
Address

Drawing style: 1
Direction: ☐ Counterclockwise
Full circle: ☐ No
Start angle: 0
End angle: 360
Radius: 100
Decimal places: 0
Distance(%): 60

Common
Style
Other
Address

Main scale len: -30
Sub. scale len: -10
Main scale num: 4
Sub. scale num: 2
Scale label: ☐
Label position: 1
Label minimum: 0
Label maximum: 10
Label color: FF111111

Common
Style
Other
Address


Address:
Device: LOCAL_HMI
Address: IB
☐ Label

(1) Common attributes


Drawing style	1: horizontal scale
	2: vertical scale
	3: circular scale
Direction	When the [drawing style] is set as [circular scale], its direction can be specified from following options. Not enabled: clockwise Enabled: counterclockwise
Full circle	Valid when [Drawing style] is circular scale.
	If checked, the circular scale will not be all-round, and the end angle can be set.
Start angle	The start angle can be set from 0 - 360° and end angle can be set from 0 - 360°
End angle	(valid if the “no” label behind [full circle] is checked).
Radius	Specify the radius of the circle. This attribute should be set when [drawing style] is [circular scale].
Decimal places	Specify the decimal places, ranging from 0 to 6.
	No decimal part if this attribute is set to 0.
Distance	When [drawing style] is [circular scale], this attribute represents the distance percentage of [scale symbol] to the object.

(2) Style

Main scale len.	Percentage length of scale to the object radius, from -100 to 100.
Sub scale len.	-100~0: ratio of the inward scale length to the radius



0~100: ratio of the outward scale length to the radius



Main scale num.	The number of main/sub scales.
Sub scale num.	
Scale label	Display the scale value or not. Enabled this attribute to display.
Label position	Specify the position of the scale value. Horizontal scale: 0-Displayed on the left. 1-Displayed on the right Vertical scale: 0-Displayed above scales. 1-Displayed below scales.
Label minimum	When [scale label] is enabled, specify the maximum and minimum of the scale value.
Label maximum	

(3) Address setting

Address	Specify [scale label], i.e., the starting address for the successive acquisition of [label minimum] and [label maximum], and if [label maximum] is set to 0, the minimum and maximum values are read from the registers corresponding to [Address] and its adjacent address, respectively.
----------------	--

(3) Shape and other attributes settings are detailed in [Chapter 4](#).

5.12 XY plot

1 Overview

The [XY plot] object is used to display two-dimensional coordinates X and Y, including values of X and Y read from the specified register. Up to 16 sets of curves can be displayed at the same time. You can observe and analyze changes of data in each register by this graph. (Not available in the current version, please use the [trend chart](#).)

2 Attributes

Click [object]→click [graph]→click [XY plot] to bring up the [XY plot] object. Drag the object to the specified [window] and double-click on the object to place it.

After selecting the object in the [window], you can set relevant attributes in the right window.

Common

Style

Address

Shape

Direction:

2

No. of channles:

1

Current channel:

1

Channel color:

FF111111

Channel style:

0

X lower limit:

0

X higher limit:

200

Y lower limit:

0

Y higher limit:

200

Data source:

Address data

Sampling ID:

1

Common

Style

Address

Shape

Reference lines:

3

Current line:

1

Line value:

3

Line color:

ff0000

Common

Style

Address

Shape

X data address:

Device:

LOCAL_HMI

Address:

IB

☐ Lable

Control address:

Device:

LOCAL_HMI

Address:

IB

☐ Lable

Address:

Device:

LOCAL_HMI

Address:

IB


☐ Lable

(1) Common attributes

Specify the orientation of the coordinate map.

- 1: Towards the left.
- 2: Towards the right.
- 3: Upwards.
- 4: Downwards.

Direction



The number of channel(s) ranges from 1 to 16.

If set to 2, the data of channel 1 will be obtained from the register corresponding to the **[Address]** and then the data of channel 2 will be obtained from the address adjacent to the **[object address]**.

No. of channel(s)

The number of the data is specified by the register corresponding to the **[control address]**.

It is similar when more than 2 channels are set.

Current channel

You can select certain channels to set parameters e.g., padding color and drawing style.

Channel color

Specify the curve color of the selected channel.

Channel style	Specify the curve style of the selected channel.
	-1: Padding in case of 1 channel and the orientation is towards the right
	0: Solid line with the width of 1
	1: Dashed line with the width of 1
	2: Dotted line with the width of 1
	3: Dashed dotted line with the width of 1
X/Y lower limit X/Y higher limit	4: Dashed double dotted line with the width of 1
	>4: Solid line with the width of n, n=value-3
Data source	The acquired XY axis data is drawn only within the s=upper and lower limits.
	[Address data]: The data of the plot will be obtained from the register corresponding to the object.
Sampling ID	[Sampling data]: The data of the plot will be obtained from the recipe database.
	When the [Data source] is set to [Sampling data], specify the sampling ID of recipe database to obtain the data.

(2) Style

Reference lines	Specify the number of reference lines. Up to 4 reference lines.
Current line	You can select a reference line and make corresponding settings, such as current value and color.
Line value	Specify the value of the selected reference line.
Line color	Specify the color of the selected reference line.

(2) Address setting

X data address	Specify the starting address to continuously acquire X-axis data.
	If this address is specified, the X-axis data is acquired from this address.
	If this address is not specified, the X-axis is used to indicate the serial number of data.
Control address	Two consecutive values were obtained from this address.
	(1) Command
	0: Redraw
	1: Clear
	2: Clear redraw
Address	(2) Number of data (single channel)
	This value defines the number of consecutive data acquired from the register corresponding to [Address].
Address	This address is the start address for continuous Y-axis data acquisition.

(4) Outline and other attributes settings are detailed in [Chapter 4](#).

5.13 Bar graph


1 Overview

The [bar graph] object displays the data of the specified register in percentage.

2 Attributes

Click [object]→click [chart]→click [bar graph] to bring up the [bar graph] object. Drag the object to the specified [window] and double-click on the object to place it.

After selecting the object in the [window], you can set relevant attributes in the right window.



(1) General attributes

Draw type	Straight: histogram round: circular diagram
Direction	Set this attribute when the [drawing type] is [straight]. [up], [down], [left], [right]
Clock direction	Valid only when [drawing type] is [round].
Full circle	If checked, the bar graph will not be all-round. The start and end angle can be set.
Start angle End angle	The start angle can be set from 0 - 360° and end angle can be set from 0 - 360°. This end angle is valid only if the “no” label behind [full circle] attribute is checked. (Note: The line between the center of the circle and the top of the circle is 0°.)
Width ratio (%)	The ratio of the width of the histogram to the width of the object or the ratio of the radius of the circular diagram to the radius of the object.
Target indicator	Whether the target value is used. 0: not used 1: used
Target value	Valid when [Target indicator] is 1.
Tolerance	Specify the tolerance of the target value. If the target value is 100 and the error is 5, then the target range is from 95 to

105. If the data is within the target range, the data is displayed by the specified [target color]. (Valid when target attribute is 1).

Origin offset Valid when the [drawing type] is a histogram, and 0 is the default origin.

(2) Style

Background color

Fill color

Border color

Lower color

Upper color

Target color

Specify relevant colors for this object.

Upper limit

Lower limit

If the data is greater than the upper limit, the object will be in upper color.

If the data is smaller than the upper limit, the object will be in lower color.

Minimum

Maximum

The data should be between the maximum and the minimum.

(3) Address setting

Address Address to obtain data.


(4) Outline and other attributes settings are detailed in [Chapter 4](#).

5.14 Meter Display

1 Overview

The [meter display] object can acquire the value in the specified register and display the data in the form of a meter.

2 Attributes



Click [object]→click [chart]→click [meter display] to bring up the [meter display] object. Drag the object to the specified [window] and double-click on the object to place it.

After selecting the object in the [window], you can set relevant attributes in the right window.

Common

Style

Shape

Address

Minimum:

0

Maximum:

400

Lower limit:

100

Higher limit:

300

Background color:

FF333333

Border color:

FF666666

Scale color:

FFFFFFF

Lower color:

FF0000

Higher color:

00FF00

Middle color:

00FFFF

Axis border color:

FF0000

Common

Style

Shape

Address

Full circle:

☐

No

Start angle:

0

End angle:

180

Background:

☒

Enable

Scale:

☒

Enable

Numeric Label:

☒

Enable

Mark:

☒

Enable

Main scale:

10

Sub. scale:

4

Scale length(1-50):

16

Circle radius(%):

35

Circle width(20-100):

25

Common

Style

Shape

Address

Address:

Device:

LOCAL_HMI

Address:

IB

☐

Label

Axis fill color:

00FF00

Pointer color:

FFD86464

Direction:

☐

Anticlockwise

Decimal places:

0

Axis radius(%):

5

Axis style:

0

Pointer width:

2

Pointer length(%):

60

(1) General attributes

Maximum and minimum

The maximum and minimum of data. Data should be between the maximum and minimum values.

Lower limit

If the data is less than the [lower limit], [lower color] is rendered.

Higher limit

If the data exceeds the [higher limit], [higher color] is rendered.

If the data is within the [lower limit] and [higher limit], [padding color] is rendered.

Background color

Border color

Scale color

Scale frame color

Lower color

Higher color

Label color

Axis border color

Specify the color of the object.

(2) Style

Full circle

If checked, the meter will not be all-round, and the end angle can be set.

Start angle

The start angle: 0 - 360°

End angle

The end angle: 0 - 360° (this attribute is valid only If all-round clock attribute is checked)

(Note: The line between the center of the circle and the top of the circle represents 0°)

Background


If enabled, the [background color] takes effect; if not, the background is transparent.

Scale

Enable or disable scales.

Numeric label

Enable or disable the numeric label.

Mark	Enable or disable marks.
Main scale	Specify the number of main/sub scales.
Sub scale	
Scale length (1-50)	The percentage of the main scale length to the size of the object: 0-50%.
Circle radius (%)	The distance percentage of the numerical value tab to the radius of the object: 0-50%.
Circle width (20-100)	The circle width is from 20 to 100%. 

(3) Address setting

Objects address	Address to obtain data.
Axis fill color	Color used to fill the inner circle.
Pointer color	Color of the pointer.
Direction	Counterclockwise/clockwise within the ranges of minimum and maximum values.
Decimal places	The decimal number of the numerical value tab.
Axis radius (%)	Axis radius as a percentage of object radius.
Axis style	Style of the axis shape. 0: circle 1: square
Pointer width	Width of the pointer.
Pointer length (%)	A percentage from 0 to 100%, and actual length of the pointer = percentage × maximum radius.

(4) Shape and other attributes settings are detailed in [Chapter 4](#).

5.15 QR code

1 Overview

Display strings by a QR code.

2 Attributes

Click [object]→click [barcodes] →click [QR Code] to bring up the [QR Code] object. Drag the object to the specified [window] and double-click on the object to place it.



After selecting the object in the [window], you can set relevant attributes in the right window.

General
Shape
Address

Type:
QRCODE

Correction:
2

Color:
FF000000

General
Shape
Address

Address:

Device:
LOCAL_HMI

Address:
IB

☐ Lable

(1) General attribute:

Type	<p>The standard by which the code is drawn.</p> <p>AZTEC Code</p> <p>QR Code</p>
Criteria	<p>This attribute is effective when the type is a [QR code].</p> <p>QR codes have the “correction ability”. Even if the code becomes dirty or broken, the data can be automatically recovered. This “correction ability” has four levels, and its strength increases with the higher level, but the size of the code also becomes larger as the amount of data increases.</p> <p>You should take the actual situation and the code size into consideration to select the appropriate level. In the factory and other environments susceptible to dirt, you can choose level Q or H. In a less dirty environment with more data is, level L is recommended. In general, most users choose level M (15%).</p> <p>Criteria 1, 2, 3, 4 for QR codes corresponding to LEVEL_L, LEVEL_M, LEVEL_Q, LEVEL_H, respectively.</p> <p>L (Low): 7% of the word code can be corrected.</p> <p>M (Medium): 15% of the word code can be corrected.</p> <p>Q (Quartile): 25% of the word code can be corrected.</p> <p>H (High): 30% of the word code can be corrected.</p>
Size	Size of the QR code.
Color	Color of the QR code.

(2) Address setting

Address	Read the characters in the address and convert these characters to a QR code.
----------------	---

(3) Shape and other attributes settings are detailed in [Chapter 4](#).

5.16 Alarm bar

1 Overview

A single-line marquee is used to display the events defined in [Event log] and having occurred.

2 Attributes

Click [Sampling/Data] → click [Alarm Bar] to bring up the [Alarm Bar] object. Drag the object to the specified [window] and double-click on the object to place it.

NO MESSAGE

After selecting the object in the [window], you can set relevant attributes in the right window.

General

Shape

Address

Marquee style:

40002005

Alarm filters type:

00FF0107

Display order:

000111

Display style:

00

Display spacing:

15

General

Shape

Address

Address:

Device:

LOCAL_HMI

Address:

IB

☐

Lable

(1) General attributes:

Marquee style	Refer to [Marquee style] in [Lamp].
	Filtering alarm events 00FF0107
	00: Initial alarm type. Value range: 00~FF
	FF: Termination alarm type. Value range: 00~FF
	01: Sorting type. 0-chronological order and 1-reverse chronological order.
	07: The specified alarm data source.
	0: All alarms in the real-time buffer.
	1: In the real-time buffer, the acknowledged alarms.
	2: In the real-time buffer, the unacknowledged alarms.
Alarm filter type	3: In the real-time buffer, the alarms that do not require acknowledgment.
	4: In the real-time buffer, the alarms that have been disarmed.
	5: In the real-time buffer, the alarms that are not disarmed
	6: In history, the acknowledged alarms.
	7: In history, the unacknowledged alarms.
	8: In history, the alarms that do not require acknowledgment.
	9: In history, the alarms that have been disarmed
	10: In history, the alarms that are not disarmed.
	11: All alarms in history.

	000111: Specify the display sequence, and whether the content is displayed. The last three bits of 111 indicate that date, time and events are all displayed 001 indicates that only the alarm event is displayed 010 means only the alarm time is displayed 100 means only the alarm date is displayed
Display order	The first three bits represent the display style 000 is default date-time-events 001 is time-date-events 010 is date-events-time 011 is time-events-date 100 is events-date-time 101 is events-time-date
Display style	00: Display style of date and events The first bit represents the date: 0-YY/MM/DD and 1-YY.MM.DD HH The second bit represents the time: 0-HH:MM:SS and 1-HH:MM
Display spacing	Spacing between different content

(2) Address setting

Address	Address of the register corresponding to the object
----------------	---

(3) Shape and other attributes settings are detailed in [Chapter 4](#).

5.17 Time/Date

1 Overview


Real-time display of time and date.

2 Attributes

Click [Object]→click [time-related] →click [Date/Time] to bring up the [Date/Time] object. Drag the object to the specified [window] and double-click on the object to place it.

2022/11/17 THU 11:45:00

After selecting the object in the [window], you can set relevant attributes in the right window.



The screenshot shows two side-by-side configuration windows. The left window has tabs for 'General', 'Shape', and 'Address'. The 'General' tab is active, showing settings for 'Display style' (1111), '12-hour clock' (unchecked), 'am/pm position' (Right), 'Text alignment' (Align center), 'Background image' (0), 'Date format' (YYYY/MM/DD), 'Time format' (HH/MM/SS), and 'Time zone' (Local time). The right window has tabs for 'General', 'Shape', and 'Address'. The 'Address' tab is active, showing settings for 'Address' (LOCAL_HMI), 'Device' (IB), and a checkbox for 'Lable'.

(1) General attributes:

Display style	<p>Display style: 1111</p> <p>Lower 3 bits represents whether date, week and time are displayed. 1 means displayed, and 0 means not displayed</p> <p>E.g., 111 means date - week – time and 101 means the date – time</p> <p>Highest bit: 1xxxx; 1 means transparent background color, and 0 means opaque background color.</p>
12-hour clock	The default is 24-hour clock. If checked, time will be displayed in 12-hour clock.
am/pm position	Valid when [12-hour clock] is checked. The default is on the left, when checked, am/pm is on the right.
Text alignment	Align center; Align left; Align right.
Background image	Background color can be replaced with a background image. Valid when the index is greater than 0.
Data format	<p>0: YYYY/MM/DD</p> <p>1: MM/DD/YYYY</p> <p>2: DD/MM/YYYY</p>
Time format	<p>0: HH/MM/SS</p> <p>1: HH/MM</p>
Time zone	Local Time; UTC time.

(2) Address setting

Address	Address of the register corresponding to the object
----------------	---

(3) Shape and other attributes settings are detailed in [Chapter 4](#).


5.18 Input Date/Time

1 Overview


Write specified date and time to the corresponding register.

2 Attributes

Click [Object]→click [time-related] →click [Input Date/Time] to bring up the [Input Date/Time] object. Drag the object to the specified [window] and double-click on the object to place it.



After selecting the object in the [window], you can set relevant attributes in the right window.



(1) General attributes:

Display style	You can choose from the following three modes.
	YYYY-MM-DD HH:MM:SS
	YYYY-MM-DD
	HH:MM:SS

(2) Address setting

Write address	<p>The date and time entered by the user will be converted into a timestamp and written to this address. The data type of the register corresponding to this address should be at least unsigned int type, so as to prevent the value of the timestamp from being out of range when the value of the time stamp is too large to write into the register.</p> <p>Select QD as the type of the local HMI register.</p> <p>When the register type is inappropriate, the date and time are displayed as 0000:00:00 00:00:00, and cannot be modified.</p>
Disable address	Specify the register used to disable the function key. When the value of the register is 0, the function key will not be disabled. Otherwise, the function key will be disabled.

(3) Shape and other attributes settings are detailed in [Chapter 4](#).

5.19 Table

1 Overview

Add a table to the window and set the border, grid and padding style.

2 Attributes

Click [object]→click [table] to bring up the [table] object. Drag the object to the specified [window] and double-click on the object to place it.

After selecting the object in the [window], you can set relevant attributes in the right window.

General
Shape

No. of rows: 3
No. of columns: 3
Current row: 1
Row height: 50
Current column: 1
Column width: 50
Fill color: 0
Gridline color: FF000000
Gridline width: 1

(1) General attributes:

No. of rows	Set the number of rows and columns.
No. of columns	
Current row	Set the height of the specified row.
Row height	
Current column	Set the width of the specified column.
Column width	
Fill color	Set the color used to fill the table.
Gridline color	Set the color of the gridlines.
Gridline width	Set the width of the gridlines.

5.20 Static/Dynamic Text

1 Overview

Add text to the window, and set the font, color, size and various related attributes.

2 Attributes

Click [object]→click [text] →click [Static text]/[Dynamic text] to bring up the [Static text]/[Dynamic text] object. Drag the object to the specified [window] and double-click on the object to place it.

After selecting the object in the [window], you can set relevant attributes in the right window.

General
Shape

Text: Text
Text color: FF000000
Background color: 0
Text alignment: Align center
Border style: None

General
Shape

Text: Text
Text color: FF000000
Background color: 0
Text alignment: Align center
Border style: None
Blink interval (ms):

(1) General attributes:

Text	Specify the content displayed by the object.
Text color	Specify the color of text content.
Background color	Specify the text background color
Text alignment	Specify the text alignment
Border style	Specify the border style. (Only dynamic text has this attribute)
Blinking interval (MS)	Specify the blinking interval. The unit is MS. (Only dynamic text has this attribute)

(2) Shape and other attributes settings are detailed in [Chapter 4](#).

5.21 Picture

1 Overview


Add picture from the system or custom picture to the window.

2 Attributes

Click [object]→click [picture] →click [Static text]/ [Dynamic text] to bring up the [Static text]/ [Dynamic text] object.

Drag the object to the specified [window] and double-click on the object to place it.

After selecting the object in the [window], you can set relevant attributes in the right window.



(1) General attributes:

Picture source	Specify the picture source: [custom picture], [library picture]
Picture type	Specify the type of the library picture.
Picture index	Specify the index of the chosen picture.
Custom picture	You need to input the number of small icons in customized pictures. Then click the button to select pictures.

Custom picture:

 2 ...


For example, the number of small icons is 2 in the right picture.

(2) GIF

Frame refresh address	If the [Picture source] is [custom picture] and the selected picture is in gif format, a certain frame in the gif picture can be displayed by setting the value of the frame refresh address register. If this register is set to 0, the 0th frame of the gif image will be displayed. If it is set to 1, the 1st frame of the gif image will be displayed...
GIF play mode	<p>Delayed: When spanning from the current frame to the specified frame, the process of the span will be played.</p> <p>Instant: When spanning from the current frame to the specified frame, the process of the span will not be played.</p> <p>Delayed loops: When spanning from the current frame to the specified frame, the process of the span will be played. Some frames after the specified frame starts to play in a loop.</p> <p>Instant loops: When spanning from the current frame to the specified frame, the process of the span will not be played. Some frames after the specified frame start to play in a loop.</p> <p>[Loop frames address] should be set to specify the number of the frames To be played in a loop.</p> <p>If the register of the loop frames address is set to 5, the 5 frames after the specified frames will be played in a loop.</p>
Loop frames address	The number of the frames to be played in a loop will be obtained from this address when loop playback is required.

(3) Shape and other attributes settings are detailed in [Chapter 4](#).

5.22 History data view

1 Overview

[History data view] displays data in the database of alarm events

2 Attributes

Click [Sampling/Data] → click [History data view] to bring up the [History data view] object. Drag the object to the specified [window] and double-click on the object to place it.

After selecting the object in the [window], you can set relevant attributes in the right window.

General
Shape
Address

Sampling ID: 0
No. of columns: 4
Current column: 1
Column content: No.
Column data format: %02d
Column font style: 1240
Column text color: FF000000
Column width: 60
Row height: 40
Display style: 00000007
Header fill color: FF0066BB
Selected row color: FF99DDFF
Gridline color: FF000000
Gridline width: 1

General
Shape
Address

Address:
Device: LOCAL_HMI
Address: IB
☐ Lable
Starting time:
Device: LOCAL_HMI
Address: IB
☐ Lable
Ending time:
Device: LOCAL_HMI
Address: IB
☐ Lable

(1) General attributes:

Sampling ID	Specify to display the information in [data sampling]. You can check all the data sampling in the module, and the ID number is the serial number of a certain data sampling.
No. of columns	Set the total number of columns in the table
Current column	You can select a column to set the corresponding attributes, such as font color, table width, etc.
Column content	Set title of the selected column
Column data format	<p>The display style of the selected column. E.g., %02d means that the data is displayed in two integers.</p> <p>Note: The set [Column data format] should correspond to the data type of the register, so as to avoid the mismatch between the displayed value and the actual value in the register.</p> <p>Float: %f, %10.2f.</p> <p>Double: %lf</p>
Column Font style	<p>Font style BIT0~2: 000, 001: bold; 010: italic; 100 underline.</p> <p>Horizontal alignment BIT3~4: 01-left-aligned; 00-center-aligned; 10-left-aligned</p> <p>Vertical alignment BIT5~6: 01-top-aligned; 00-center-aligned; 10-bottom-aligned</p> <p>Font size BIT 8~15:</p>

	E.g., 1240(hexadecimal) means that font size is 18, font style is bold, and alignment is horizontally centered and vertically bottom.
Column text color	Set the text color of the selected column
Column width	Set the width of the selected column
Row height	Set the height of each row
Display style	0x00000001 // horizontal lines
	0x00000002 // vertical lines
	0x00000004 // the title bar
	0x00000008 // the scrolling register control function
	0x00000010 // the database management function
	0x00000020 // data in descending order
	0x00000040 // data in ascending order
	0x00000080 // data automatic update
	0x00000100 // the confirmation control function
	0xF0000000 // how to display time
	F position
	0:HH:MM:SS;1:HH:MM;2:DD:HH:MM;3:HH;
Header fill color	0x0F000000 // how to display date
	F position:
	0:MM/DD/YY,1:DD/MM/YY, 2:DD.MM.YY, 3:YY/MM/DD
Header fill color	Specify the padding color of title column.
Selected row color	Specify the padding color of the selected row.
Gridline color	Specify the gridline color
Gridline width	Specify the gridline width

(2) Address

Address	After setting, you can use the [function key] to control refresh and other operations.
Starting time	Filter the displayed data according to the data time and the set starting/ending time.
Ending time	

(3) Shape and other attributes settings are detailed in [Chapter 4](#).

5.23 Recipe view

1 Overview

The [recipe view] can display relevant information in the recipe database.

2 Attributes

Click [Sampling/Data] →click [recipe view] to bring up a [recipe view] object.

After selecting the object in the [page], you can set relevant attributes in the right window. Drag the object to the specified [window] and double-click on the object to place it.

After selecting the object in the [window], you can set relevant attributes in the right window.

General
Shape
Address

Recipe database ID: 1
No. of columns: 4
Current column: 1
Column field ID: 1
Column data format: %02d
Column font style: 1240
Column text color: FF000000
Column width: 60
Row height: 40
Display style: 00000007
Header fill color: FF0066BB
Selected row color: FF99DDFF
Gridline color: FF000000
Gridline width: 1

General
Shape
Address

Address:
Device: LOCAL_HMI
Address: IB
☐ Lable

(1) General attributes

Recipe database ID	Specify which database file in the recipe database is displayed. You can check which database files are available in the [recipe database] module, and the ID number is the database serial number.
No. of column	Set the total number of columns
Current column	You can select a column to set the corresponding attributes, such as font color, table width, etc.
Column field ID	Set the displayed field of the current column.
Column data format	<p>The display style of the selected column. E.g., %02d means that the data is displayed in two integers.</p> <p>Note: The set [Column data format] should correspond to the data type of the register, so as to avoid the mismatch between the displayed value and the actual value in the register.</p> <p>Float: %f, %10.2f.</p> <p>Double: %lf</p>
Column font style	<p>Font style BIT0~2: 000, 001: bold; 010: italic; 100 underline</p> <p>Horizontal alignment BIT3~4: 01-left-aligned; 00-center-aligned; 10-left-aligned</p>

	Vertical alignment BIT5~6: 01-top-aligned; 00-center-aligned; 10-bottom-aligned
	Font size BIT 8~15: E.g., 0x1240 means that font size is 18, font style is bold, and alignment is horizontally centered and vertically bottom.
Column text color	Set the text color of the selected column.
Column width	Set the width of the selected column
Row height	Set the height of each row
Display style	0x00000001 // horizontal lines 0x00000002 // vertical lines 0x00000004 // the title bar 0x00000008 // the scrolling register control function 0x00000010 // the database management function 0x00000020 // data in descending order 0x00000040 // data in ascending order 0x00000080 // data automatic update 0x00000100 // the confirmation control function 0xF0000000 // how to display time F position 0:HH:MM:SS;1:HH:MM;2:DD:HH:MM;3:HH; 0x0F000000 // how to display date F position: 0:MM/DD/YY,1:DD/MM/YY,2: DD.MM.YY,3: YY/MM/DD
Header fill color	Specify the padding color of the header.
Selected row color	Specify the padding color of the selected row
Gridline color	Specify the gridline color.
Gridline width	Specify the gridline width.

(2) Address

Address	There is no need to set the address in current version.
----------------	---

(3) Shape and other attributes settings are detailed in [Chapter 4](#).

5.24 Operation log view

1 Overview

[Operation log view] can be used to view user operation logs.

2 Attributes

Click [Sampling/Data]→click [operation log view] to bring up an [operation log view] object. Drag the object to the specified [window] and double-click on the object to place it.

After selecting the object in the [window], you can set relevant attributes in the right window.

General
Shape
Address

No. of columns: 7
Current column: 0
Column content: Date
Column font style: 1240
Column text color: FF000000
Column width: 100
Row height: 40
Display style: 00000007
Header fill color: FF0066BB
Selected color: FF99DDFF
Gridline color: FF000000
Gridline width: 1

General
Shape
Address

Address:
Device: LOCAL_HMI
Address: IB
☐ Lable

(1) General attributes

Operation log address	Specify the source of the operation log
Number of columns	Set the total number of columns
The selected column	You can select a column to set the corresponding attributes, such as font color, table width, etc.
Content	Set content of the selected column
Text style	<p>Font style BIT0~2: 000, 001: bold; 010: italic; 100 underline</p> <p>Horizontal alignment BIT3~4: 01-left-aligned; 00-center-aligned; 10-left-aligned</p> <p>Vertical alignment BIT5~6: 01-top-aligned; 00-center-aligned; 10-bottom-aligned</p> <p>Font size BIT 8~15:</p> <p>E.g. 0x1240 means that font size is 18, font style is bold, and alignment is horizontally centered and vertically bottom.</p>
Text color	Set the text color of the selected column
Table width	Set the width of the selected column
Row height	Set the height of each row

	0x00000001 // horizontal lines
	0x00000002 // vertical lines
	0x00000004 // the title bar
	0x00000008 // the scrolling register control function
	0x00000010 // the database management function
	0x00000020 // data in descending order
	0x00000040 // data in ascending order
List display style	0x00000080 // data automatic update
	0x00000100 // the confirmation control function
	0xF0000000 // how to display time
	F position
	0:HH:MM:SS;1:HH:MM;2:DD:HH:MM;3:HH;
	0x0F000000 // how to display date
	F position:
	0: MM/DD/YY, 1: DD/MM/YY, 2: DD.MM.YY, 3: YY/MM/DD
Padding color	Specify the padding color of title column
Row color	Specify the padding color of the selected row
Gridline color	Specify the gridline color
Gridline width	Specify the gridline width

(2) Address

Address	There is no need to set the address in current version.
----------------	---

(3) Shape and other attributes settings are detailed in [Chapter 4](#).

5.25 Alarm view/Event view

1 Overview

[Alarm view]/[Event view] can be used to view alarm information.

2 Attributes

Click [Sampling/Data] → click [Alarm view]/[event view] to bring up an [Alarm view]/[Event view] object. Drag the object to the specified [window] and double-click on the object to place it.

After selecting the object in the [window], you can set relevant attributes in the right window.

Alarm

Display

Shape

Address

No. of columns:

8

Current column:

0

Column content:

No.

Column font style:

1240

Column text color:

FF000000

Column width:

60

Row height:

40

Display style:

03000007

Header fill color:

FF0066BB

Selected color:

FF99DDFF

Gridline color:

FF000000

Gridline width:

1

Alarm

Display

Shape

Address

Starting type:

0

Ending type:

255

Alarm status:

All states

Alarm type:

History

Alarm sequence:

Chronological

Alarm

Display

Shape

Address

Address:

Device:

LOCAL_HMI

Address:

IB

☐ Lable

(1) Alarm

Starting type	Filter the displayed alarm event starting type.
Ending type	Filter the displayed alarm event ending type. The object will display the alarm events from the starting type to the ending type.
Alarm status	You can select from the following options: [all states], [confirmed], [unconfirmed], [no confirmation required], [cleared], [not cleared]. The object will only display the contents of the selected option.
Alarm type	You can select from [real-time], [history] and [all]. All alarms will be displayed if you choose [all] and [alarm status] will become invalid.
Alarm sequence	You can select from [chronological] and [time reversal].

(2) Display

No. of columns	Set the total number of columns in the table.
Current column	You can select a column to set the corresponding attributes, such as font color, table width, etc.
Column content	Set content of the selected column.
Column font style	Font style BIT0~2: 000, 001: bold; 010: italic; 100 underline Horizontal alignment BIT3~4: 01-left-aligned; 00-center-aligned; 10-left-aligned Vertical alignment BIT5~6: 01-top-aligned; 00-center-aligned; 10-bottom-aligned Font size BIT 8~15: E.g., 0x1240 means that font size is 18, font style is bold, and alignment is horizontally centered and vertically bottom.
Column text color	Set the text color of the selected column.
Column Width	Set the width of the selected column.
Row height	Set the height of each row.
Display style	0x000000001 // horizontal lines 0x000000002 // vertical lines

0x00000004 // the title bar
0x00000008 // the scrolling register control function
0x00000010 // the database management function
0x00000020 // data in descending order
0x00000040 // data in ascending order
0x00000080 // data automatic update
0x00000100 // the confirmation control function
0xF0000000 // how to display time
F position
0: HH:MM:SS;1:HH:MM;2:DD:HH:MM;3:HH;
0x0F000000 // how to display date
F position:
0:MM/DD/YY,1:DD/MM/YY,2: DD.MM.YY,3: YY/MM/DD

Header fill color	Specify the padding color of the title column.
Selected row color	Specify the padding color of the selected row.
Gridline color	Specify the gridline color.
Gridline width	Specify the gridline width.

(3) Address

Address	There is no need to set the address in current version.
----------------	---

(4) Shape and other attributes settings are detailed in [Chapter 4](#).


5.26 Trend chart

1 Overview

[Trend chart] can be used to display the trend of the data corresponding to the sampling id in the data sampling database over a period of time.

2 Attributes

Click [Sampling/Data] → click [Trend chart] to bring up an [Trend chart] object. Drag the object to the specified [window] and double-click on the object to place it.



After selecting the object in the [window], you can set relevant attributes in the right window.

GeneralShapeAddress

Sampling ID:1

No. of channels:4

Time span(ms):300000

Sampling interval:4000

Fill color:ffa9a9a9

Gridline color:ff545454

Current channel:1

Channel attributes

Minimum:0

Maximum:10

Channel name:CH1

Curve color:ffff0000

GeneralShapeAddress

Channel ID address:

Device:LOCAL_HMI

Address:IB

☐ Lable

Limit address:☐ Enable

Minimum address:

Device:LOCAL_HMI

Address:IB

☐ Lable

Maximum address:

Device:LOCAL_HMI

Address:IB

☐ Lable

(1) General attributes

Sampling ID	Specify the source of the operation log
No. of columns	Set the total number of columns
Time span(ms)	You can select a column to set the corresponding attributes, such as font color, table width, etc.
Sampling interval	Set content of the selected column
Fill color	Font style BIT0~2: 000, 001: bold; 010: italic; 100 underline
Gridline color	Set the text color of the selected column
Current channel	Set the width of the selected column
Minimum	Set the height of each row
Maximum	0x00000001 // horizontal lines
Channel name	Specify the padding color of title column
Curve color	Specify the padding color of the selected row

(2) Address

Address	There is no need to set the address in current version.
----------------	---

(3) Shape and other attributes settings are detailed in [Chapter 4](#).

5.27 Horizontal Pipeline/Vertical Pipeline

1 Overview

[Horizontal Pipeline]/ [Vertical Pipeline] can be used with [Pipeline Connector] to build process flow diagrams.

2 Attributes

Click [Object] → click [Horizontal Pipeline]/ [Vertical Pipeline] to bring up an [Horizontal Pipeline]/ [Vertical Pipeline] object. Drag the object to the specified [window] and double-click on the object to place it.

After selecting the object in the [window], you can set relevant attributes in the right window.

Address

Style

Position

Liquid level:

Device:

LOCAL_HMI

Address:

IB

☐ Lable

Direction control: (Greater than 0: rightward)

Device:

LOCAL_HMI

Address:

IB

☐ Lable

Flowing control:

☐ Reverse

Device:

LOCAL_HMI

Address:

IB

☐ Lable

Address

Style

Position

Liquid shape:

Rounded rectangle

Liquid color:

1

FF0000DD

Liquid fill color:

1

0

Liquid length:

26

Liquid width:

10

Library picture:

1

Custom picture:

...

Flow speed(ms):

300


Word flowing:

Word flowing style:

font-size: 12;color:blue;

(1) Address

Liquid level



When the value of the register is 1:

a. if there are 2 custom pictures, the second picture will be displayed in the pipeline.



b. if there is only one custom picture, the content set in [word flowing] attribute will be displayed in the pipeline.

Direction control

Set the state of the register value relative to 0 to specify the flowing direction.

When the value of the register is greater than 0, the direction is right (up for vertical pipeline.)

When the value of the register is equal to 0, the direction is left (down for vertical pipeline.)

Flowing control

Set the value of the register to specify whether to flow.

Reverse

Checked:


Flow if the value of the register of [Flowing control] is 0. Not flow if the value is 1.

Unchecked:
Flow if the value of the register of [Flowing control] is 1. Not flow if the value is 0.


(2) Style

Liquid shape	Choose from [Rounded rectangle] and [Arrow].
Liquid color	Valid when [word flowing] is not used to simulate liquid flow. Specify the color of the flowing liquid. You can set the color of the liquid in different working states: If you need to set the liquid color to color 1, you can set the value of the [flowing control] register to 1; If you need to set the liquid color to color 2, you can set the value of the [flowing control] register to 2; ... Up to ten colors can be set in this version.
Liquid fill color	Valid when [word flowing] is not used to simulate liquid flow. Specify the color of the flowing liquid. You can set the color of the liquid in different working states: If you need to set the liquid fill color to color 1, you can set the value of the [flowing control] register to 1; If you need to set the liquid fill color to color 2, you can set the value of the [flowing control] register to 2; ... Up to ten colors can be set in this version.
Liquid length	Set the length of the liquid.
Liquid width	Set the width of the liquid.
Library picture	unspecified: do not use an image as the icon. numbers: use the default image specified by the system to draw the icon.

Customize the picture used to display in the pipeline:
You need to input the number of small icons in customized pictures. Then click the button to select pictures.



For example, the number of small icons is 2 in the following picture.



Custom picture

Note:
a. If the number of small icons is set to 2, the icons should be placed vertically, but not placed horizontally as the following picture.



b. The icons will be rotated 90° clockwise automatically. Horizontal piping diagrams can be used in vertical pipeline like horizontal pipeline.

Flow speed(ms)	The unit is millisecond. The smaller the value, the faster the flow.
Word flowing	Set the word used to simulate liquid flowing. When this attribute is set to empty, the liquid flow is simulated by specifying the [liquid shape].
Word flowing style	Set the font size and color when using word to simulate liquid flowing.

(3) Shape and other attributes settings are detailed in [Chapter 4](#).

5.28 Pipeline Connector


1 Overview

[Pipeline Connector] can be used with [Horizontal Pipeline]/ [Vertical Pipeline] to build process flow diagrams.

2 Attributes

Click [Object] → click [Pipeline Connector] to bring up an [Pipeline Connector] object. Drag the object to the specified [window] and double-click on the object to place it.

After selecting the object in the [window], you can set relevant attributes in the right window.



(1) Display

Custom picture	Customize the picture used to display in the pipeline: You need to input the number of small icons in customized pictures. Then click the button to select pictures.
Liquid level	There is no need to set this attribute in current version.

(2) Shape and other attributes settings are detailed in [Chapter 4](#).

5.29 Vector Graphics

1 Overview


[Vector Graphics] can be used to edit vector graphics. You can place the edited vector graphics like an object.

Basic graphics such as lines, rectangles, ellipses, curves, polygons are integrated in the editing function.

2 Instructions for use

Click [Project] → click [Vector Graphics] to bring up an [Vector Graphics] object. Drag the object to the specified [window] and double-click on the object to place it.

After selecting the object in the [window], you can click [editor] in the right window to enter the editing interface.



The instructions for each basic graphic are as follows:

(1) line

Click the [Line] button to enter the line drawing mode. Press and hold the left mouse button to start drawing a line. Move the mouse to draw. Release the left button to finish drawing the line.

(2) rectangle

Click the [Rectangle] button to enter the rectangle drawing mode. Press and hold the left mouse button to start drawing a rectangle. The position where the left mouse button is clicked is the upper left corner of the rectangle. Release the left mouse button to end drawing. The position where the left mouse button is released is the lower right corner of the square.

(3) ellipse

Click the [ellipse] button to enter the ellipse drawing mode, click the left mouse button to start drawing a circle and drag the mouse to change the size and shape of the circle, release the left mouse button to finish drawing.


(4) curve

Click the [curve] button to enter the curve drawing mode. The left-click position is the starting point of the current small curve, and the left-click position is the end point of the current small curve. Press and hold the left button and drag to change the curvature and length of the curve. , direction, etc. Release the left button to complete the current curve drawing, repeat the above process to draw the next curve, and click the right button to end the curve drawing.

(5) polygon

Click the [Polygon] button to enter the polygon drawing mode. Left-click is the starting point of one side, and the next click is the end point of one side. Repeat the above process. Right-click to end drawing and the starting point and the end point will be automatically connected.

3 Attributes introduction



Line color	Sets the line color for drawing graphs.
Fill color	Sets the fill color of the drawn graphics area. The filled area does not exist for a line. It is a closed area for a closed graphic. For an open curve, it is the area enclosed by the auxiliary line and the curve when drawing.
Layer	Set the layer where the graph is located. The larger the number, the higher the graph will be displayed.
Opacity	Set the opacity of the graphics. The maximum value is 100 (completely opaque) and the minimum value is 0 (completely transparent).
Line style	Invalid.
Line width	Set the line width used when drawing.
Start X Start Y	Set the X value and Y value of the start point and end point of the graph (i.e., the upper left corner and lower right corner of the selected box around the graph).
End X End Y	
Width	Set the width and height of a rectangle.
Height	
Corner radius	Set the corner radius of a rectangle. The rectangle is a rounded rectangle when the [corner radius] is greater than 0.
X radius	Set the X and Y radius of an ellipse.
Y radius	

5.30 Media Player

1 Overview

[Media Player] can be used to play local video files in mp4 and avi formats. (Not available in the current version)

2 Attributes settings

Source address	Store the address of the video to be played. (e.g., ./mnt/exUDISK/test3.mp4)
Play control address	The register to control the status of play. 0: play; 1: pause; 2: fast forward; 3: backward; 4: previous episode; 5: next episode; 6: repeat; 7: stop.
Progress control address	Control the play progress. The unit is second.
Default play url	Set the default url to be played. If [Source address] is empty, the video corresponding to the url will be played.
Auto play	Autoplay or not.

Chapter 6 Others

6.1 Input method

The preset input method is the default input method in the system.

6.2 Download project

For detailed description, please refer to [Chapter 2](#).

6.3 Register address setting

In the software, it is frequently needed to set the register address. The register address setting instructions are as follows.

Device: LOCAL_HMI
Address: IB
☐ Lable

Device: RECIPE_DB
DB Name: basic
DB Item: item1

Device: siemen S1200_1
Address: I
☐ Lable
Num:
Freq:

Device	Address: The left edit box	Address: The right edit box
LOCAL_HMI (Local register)	Specify the register type.	Range:
	IB: Bit status output register;	IB: 0 - 10255
	QB: Bit status input-output register;	QB: 0 - 10255
	IW: 16-bit word output register;	IW: 0 - 10255
	QW: 16-bit word input-output register;	QW: 0 - 10255
	ID: 32-bit double-word output register;	ID: 0 - 5127
	QD: 32-bit double-word input-output register;	QD: 0 - 5127
	IF: 32BIT-float output register;	IF: 0 - 5127
	QF: 32BIT-float input and output register;	QF: 0 - 5127
	IDD: 64BIT-double output register;	IDD: 0 - 2563
	QDD: 64BIT-double input and output register.	QDD: 0 - 2563
	IS: string input register	IS: 0-10255
	QS: string output register	QS: 0-10255
	user: set the security level of the object	
RECIPE_DB (Local recipe register)	Specify the recipe database.	Specify a field in the recipe database.
	You can define the recipe database in the [recipe database] module.	There can be multiple fields in a recipe database, and each field corresponds to a set of data. You can define the field and preset the data corresponding to the field in the [recipe database] module.
Modbus_com m (commonly used register)	Specified registers:	
	Coil (DO): 0x, may be read or written by HMI.	
	Discrete inputs (DI): 1x, may only be read by HMI.	

Analog inputs (AI): 3x, may only be read by HMI.

Analog outputs (AO): 4x, may be read or written by HMI.

AIW: Input registers (WORD)

AOW: Output registers (WORD)

AID: Input registers (DWORD)

AOD: Output registers (DWORD)

AI4F: Input registers (FLOAT)

AO4F: Output registers (FLOAT)

AI8F: Input registers (DOUBLE)

AO8F: Output registers (DOUBLE)

AIS: Input registers (STRING)

AOS: Output registers (STRING)

Note: When the device is selected as an external device, [Num] is the number of registers. [Freq] is the time interval for register refresh, and the unit is millisecond.

6.4 JavaScript function

JavaScript provides additional functionality required outside of the application. When the HMI is running, the JavaScript can be automatically executed, and it is responsible for the communication between the user and the project. This chapter mainly introduces the syntax of JS scripts, how to use and edit and other functions.

1 Edit

There are two ways to edit the JavaScript in the current version.

a) Click [Project] in the menu bar → click [Macro] to bring up the [Macro] interface. You can edit JavaScript in the pop-up window.

b) Edit JavaScript files in JavaScript editor such as Notepad++, Windows Notepad, UltraEdit, VS Code. Import the JavaScript files in the [Macro] interface.

[Macro] function introduction:

New	Click the [new] button in the [Macro] interface to create a new JavaScript file.
Save	Click the [Save] button in the [Macro] interface to save the JavaScript file.
Delete	Click the [Delete] button in the [Macro] interface to delete the selected JavaScript file.
Import Export	Click the [Import]/[Export] button in the [Macro] interface to import or export the selected JavaScript file.
Current JS file	Select to switch the current script through the combo box.
JS setup	Click the [JS setup] button → Double-click the JS file that you want to modify → select a JS file for the selected window through the combo box.
Tab	equal to 4 spaces.
End	jump to the end of the current line.

Backspace	Delete the character before the cursor or selected characters.
Delete	Delete the character after the cursor or the selected characters.
F3/F4	Search the selected characters in the content below/above.
Copy/Paste	Press [Ctrl]+[C] to copy or [Ctrl]+[V] to paste after selecting some characters. You can also right click and select to copy or paste after selecting some characters.
Compile	<p>Compile and run JS functions (To run JS functions, you need to call the function separately, such as: fn(n1,n2,n3);).</p> <p>Support compiler and running error reporting by highlighting the error line. (Note: When a script is set as a window script, the function that is called separately will run immediately when going to this window. If you don't want to run immediately, please note the call after debugging.)</p>
Undo/Redo	Undo: [Ctrl]+[Z]; Redo: [Ctrl]+[Y]

2 Syntax

Here we only introduce some basic syntax commonly used when editing scripts. If you want to learn more about JavaScript, you can search for related tutorials on the Internet.

Basic syntax

Semicolon: used to separate statements. Usually, we add a semicolon at the end of each executable statement.

Example:

```
a = 5;
b = 6;
c = a + b;
```

Comments: Single line comments start with //. Multi-line comments start with /* and end with */.

Example:

```
/*
The code below will change
the heading with id = "myH"
and the paragraph with id = "myP"
in my web page:
*/
Var x = 5;    // Declare x, give it the value of 5
```

Declare a variable

Declare variables with the var keyword.

Example: var name,age;

You can assign a value to a variable using the = operator when you declare it or after the declaration and before accessing it.

Example:

```
name = "David";
```

	<pre>var age = 30;</pre>
	<p>A JavaScript function is defined with the function keyword, followed by a name, followed by parentheses ().</p> <p>Function without parameters:</p> <pre>function functionname() { // the code to be executed }</pre> <p>Function with parameters: The parentheses may include parameter names separated by commas:</p> <p>(parameter1, parameter2, ...)</p> <pre>function myFunction(var1,var2) { // the code to be executed }</pre> <p>Function arguments are the values received by the function when it is invoked. Parameters and arguments must appear in a consistent order.</p> <p>Example: myFunction(argument1,argument2)</p> <pre>function myFunction(a,b) { x=a+b }</pre> <p>To invoke the function above:</p> <pre>myFunction(2,3);</pre> <p>Functions often compute a return value. The return value is "returned" back to the "caller":</p> <pre>function myFunction() { var x=5; return x;//return the return value }</pre> <p>To invoke the function above:</p> <pre>var myVar=myFunction();</pre>
Function syntax	
	<p>Similar to C conditional statements</p> <p>if</p> <p>if...else</p> <p>switch</p> <p>for</p> <p>while</p>
Conditional statements	

3 common functions

In HMI software, JS functions are often used in objects such as function keys, switches, and numeric. There are

usually two ways to use JS functions:

a) pre-defined JavaScript commands

Switch window

Switch windows: name of the window (ID_Title)

For example, when the function key is pressed, jump to the window with ID number 1 can be set as follows:

JS command:

Command Type:

Window ID:

Go back to the previous page:

JS command:

Command Type:

Window ID:

Open pop-up window

Open a pop-up window: name of the window (ID_Title)

For example, when the function key is pressed, open the window with ID number 2 can be set as follows:

JS command:

Command Type:

Window ID:

Close pop-up window

Close a pop-up window: name of the window (ID_Title)

JS command:

Command Type:

Window ID:

b) custom JavaScript commands

Add user-defined functions in common.js

Refer to the following function

```
function closedlg200{
Hmiregs.SetReg(0,2,9820,143);
}
```

Use a user-defined function in an object

JS command:

Command Type:

Function Name:

When the command type is set to [execute function], the JavaScript window will pop up automatically. Double-click the function name to select it. Or you can click [...] to enter the JavaScript window.


4 Hmiregs object

A JS object Hmiregs is encapsulated inside the HMI configuration software, and some common operations can be realized through this object.

Hmiregs.SetReg(int devid,int regtype,unsigned long reg,var value);

Parameters' introduction:

devid: Station No. of the device. The station number can be set in [System Parameters]. The station number of the local device is 0.



regtype: the type of the register

Local HMI devices:

IB-0	QB-1	IW-2	QW-3	ID-4	QD-5	IF-6
QF-7	IDD-8	QDD-9	IS-10	QS-11		

Set the value of a register

Siemen S200:

I-0	Q-1	M-2	S-3	SM-4	V-5	L-6
IB-7	QB-8	MB-9	SB-10	SMB-11	VB-12	LB-13
IW-14	QW-15	MW-16	SW-17	SMW-18	VW-19	LW-20
AIW-21	AQW-22	T-23	C-24	ID-25	QD-26	MD-27
SD-28	SMD-29	VD-30	LD-31	VF-32	LF-33	MS-34
SMS-35	VS-36					

reg: the address of the register

value: the value to set

For example,

(1) Set the local HMI device QW100 register value to 6.

Hmiregs.SetReg(0,3,100,6);

(2) Set the value in VW804 register of Siemens S200 to 2.

Hmiregs.SetReg(1,19,804,2); //It is assumed that the station number of the equipment is 1.

(3) Set the value in M5.7 register of Siemens S200 to 1.

Hmiregs.SetReg(1,2,47,1); //It is assumed that the station number of the equipment is 1.

	<p>47(argument3): address= integral part*8+decimal places value when reading/writing registers in JavaScript</p> <p>(4) Set strings into the IS8202 register of the local device</p> <pre>Hmiregs.SetReg(0,10,8202,"username");</pre> <p>Hmiregs.SetReg(0,10,8202,""); //clear the IS8202 register.</p>
	<p>Hmiregs.GetReg(int devid,int regtype,unsigned long reg);</p> <p>For the meaning of the parameters, see the description in the [Set the value of a register] above.</p> <p>For example,</p> <p>(1) read the value in QW100 register of the local device</p> <pre>var v = Hmiregs.GetReg(0,3,100);</pre> <p>(2) read the value in VW804 register of Siemens S200</p> <pre>var v = Hmiregs.GetReg(1,19,804);</pre> <p>//It is assumed that the station number of the equipment is 1.</p> <p>(3) read the value in M5.7 register of Siemens S200</p> <pre>var v = Hmiregs.GetReg(1,2,47);</pre> <p>//It is assumed that the station number of the equipment is 1.</p> <p>(4) read the string in VS2001 register of Siemens S200</p> <pre>var str = Hmiregs.GetReg(1,36,2001,20);</pre> <p>//argument4: start from the VS2001 address, read 20 bytes continuously.</p>
Read registers	
	<p>Function: Hmiregs.OpenPage(var pageID,var type);</p> <p>Parameters' introduction:</p> <p>pageID: ID of the window to be opened.</p> <p>type: type of the window to be opened. Windows-0; Pop-up window-1.</p> <p>For example,</p> <pre>Hmiregs.OpenPage(5,0);</pre> <p>//open the window with ID number 5</p> <pre>Hmiregs.OpenPage(6,1);</pre> <p>//open the window with ID number 6</p> <p>You can also open a window or a pop-up window using the pre-defined command.</p> <p>Details referring to [pre-defined JavaScript commands].</p>
Open a window/pop-up window	
	<p>Close the pop-up window with ID number 20:</p> <pre>function closedlg20() { Hmiregs.SetReg(0,2,9820,143); }</pre> <p>You can set the JS command of some function key to closedlg20() so that the pop-up window will be closed when you click the function key.</p> <p>Parameters' introduction:</p> <p>'0', '2', '143' is fixed. Only the 3rd parameter changes.</p>
Close a pop-up window	

3rd parameter: 9800+the ID of the pop-up window to be closed

For example,

Hmiregs.SetReg(0,2,9821,143); //close the window with ID number 21

Hmiregs.SetReg(0,2,9809,143); //close the window with ID number 9

You can also close a pop-up window using the pre-defined command.

Details referring to [pre-defined JavaScript commands].

Hmiregs.MSleep(100); //stop the program for 100 MS. Delay time is specified in milliseconds.

When using this function, the window will be blocked and the click will not be responded. It is not recommended to set an excessive time.

setTimeout("functiontobecalled()",delaytime); //Delay time is specified in milliseconds.

Function: delay a function call

Delay function

For example, you can delay setting the value of a register for 1 second.

function percent()

{

var v = Hmiregs.GetReg(0,2,780);

Hmiregs.SetReg(0,2,780,v+1);

if(v < 100)

setTimeout("percent()",1000); //call the function itself

}

DeleteSample(sid,eid,val)

The following are the parameters-

sid: -1 means to delete all records. If sid is greater than or equal to 0, delete the entries equal to val in the sampling records of sid, and the deletion range is sid to eid.

Delete a sampling record

For example, delete the entry whose data is 1 in sample id0 (that is, the first data sample), and the deletion range includes the content of sample id 1-15.

function exp()

{

Hmiregs.DeleteSample(0,15,1);

}

Hmiregs.analysisData(method,sid,channel)

The following are the parameters-

sid: sampling id to be analyzed.

Data analysis

channel: 0 for multi-channel sampling. You can specify the channel to be analyzed when choosing single channel.

For example, analyze the data in first channel of the first sampling id.

function exp()


```

{
    var min,max,avg,val;
    min = Hmiregs.analysisData(0,0,0);
    max = Hmiregs.analysisData(1,0,0);
    avg = Hmiregs.analysisData(2,0,0);
    val = Hmiregs.analysisData(3,0,0);
}

```

5 Functions related to PDF

Some PDF-related functions are encapsulated inside the HMI configuration software.

pdf.HPDF_Open	<p>Example: pdf.HPDF_Open(2000,1000)</p> <p>Create a pdf with a width of 2000 and a height of 1000 and open the created pdf. The font "Helvetica" is used by default (the font cannot display Chinese by default), the default font size is 12, the default line width is 1.0, and the RGB of the line is (0, 0 ,0).</p>
pdf.HPDF_Save	<p>Example: pdf.HPDF_Save("/media/usb/test.pdf")</p> <p>Save the pdf to "/media/usb/test.pdf" as test.pdf.</p>
pdf.HPDF_Close	<p>Example: pdf.HPDF_Close()</p> <p>Close the pdf.</p>
pdf.HPDF_AddOnePage	<p>Example: pdf.HPDF_AddOnePage(800,1000)</p> <p>Add a page with a width of 800 and a height of 800 to the pdf and switch to that page. The line width and color are the same as the previous page.</p>
pdf.HPDF_SwitchToPage	<p>pdf.HPDF_SwitchToPage(pid)</p> <p>Switch to the page with pid.</p> <p>pid: the id of the page to be switched. The id of the first page created is 0 by default.</p>
pdf.HPDF_LoadTTFfont	<p>pdf.HPDF_LoadTTFfont(path)</p> <p>Load a font. The default font cannot display Chinese characters. There is a font named ttf that can display Chinese characters. You can load the font by setting the path to path=" /usr/share/SDL_UI/fonts/STSONG.TTF" .</p>
pdf.HPDF_SetFontSize	<p>pdf.HPDF_SetFontSize(size): set the font size.</p>
pdf.HPDF_DataTableTimeFilter	<p>pdf.HPDF_DataTableTimeFilter(flag)</p> <p>Save the start time of the database filtering to filter data before the start time.</p> <p>flag: 0-alarm; 1-event; 2-recipe; 3-sampling; 4-record</p> <p>If you save the history database, you don't need to use this function.</p>

pdf.HPDF_AlarmTable(starttype,endtype,sorttype,source,vnum,str_vwidth)

Save the content in the alarm database to the pdf.

The following are the parameters-

starttype: the start alarm type to be filtered.

endtype: the end alarm type to be filtered.

sorttype: 0- chronologically, most recent first; 1- in reverse chronological order, most recent last.

source: the specified data source

0: All alarms in the real-time buffer.

1: In the real-time buffer, the acknowledged alarms.

2: In the real-time buffer, the unacknowledged alarms.

3: In the real-time buffer, the alarms that do not require acknowledgment.

4: In the real-time buffer, the alarms that have been disarmed.

5: In the real-time buffer, the alarms that are not disarmed

6: In history, the acknowledged alarms.

7: In history, the unacknowledged alarms.

8: In history, the alarms that do not require acknowledgment.

9: In history, the alarms that have been disarmed

10: In history, the alarms that are not disarmed.

11: All alarms in history.

12: all alarms in the real-time buffer and history.

vnum: the number of the columns in the table

str_vwidth: the width of the column, separated by commas.

Example:

pdf.HPDF_AlarmTable

```
function save_hisalarm()
{
    var year,month,day,h,m,s;
    pdf.HPDF_Open(920,1000);
    pdf.HPDF_LoadTTFfont("/usr/share/SDL_UI/fonts/STSONG.TTF");
    pdf.HPDF_AlarmTable(0,255,0,11,6,"100,100,100,100,180,320");//6为列数 11为历史记录中的所有

    g_Date.setTime(Date.now());
    if(g_using_UTC){
        year = g_Date.getUTCFullYear();
        mon = g_Date.getUTCMonth() + 1;
        dd = g_Date.getUTCDate();
        h = g_Date.getUTCHours();
        m = g_Date.getUTCMinutes();
        s = g_Date.getUTCSeconds();
    }
    else{
        year = g_Date.getFullYear();
        mon = g_Date.getMonth() + 1;
        dd = g_Date.getDate();
        h = g_Date.getHours();
        m = g_Date.getMinutes();
        s = g_Date.getSeconds();
    }
    var ret = pdf.HPDF_Save("/media/usb/" + "Alarm_his" + "_" + year + "-" + mon + "-" + dd + "_" + s);
    pdf.HPDF_Close();
}
```

pdf.HPDF_SampleTable

pdf.HPDF_SampleTable(startsid,vnum,sidnum,sample_format,real,stime,etime,method,val)

Save the content in the recipe database to the pdf.

The following are the parameters-

started: the start id, greater than or equal to 1;

vnum: number of the column in the table;

sidnum: number of the sid;

sample_format: the data format of each sid, separated by commas (Just specify that the data format of the sampling channel involved is different from the format specified in each column in the [history data view]);

real: 1 when pdf.HPDF_DataTableTimeFilter(flag) is used; otherwise 0.

stime: starting time to export data.

etime: ending time to export data

method: method to export data. 0-chronologically; 1-by data.

val: export records where startid = val.

example:

```
var g_Date = new Date();
var g_using_UTC = 0;
var sample_format = "%10.2f,%10.2f,%10.2f,%10.2f,%10.2f,%10.2f,%10.2f,%10.2f,%10.2f,%10.2f,%d,%d,%10.4f,%10.4f,%d,%d,%d,%d,%d,%d";
function save_histsample()
{
    var year,mon,dd,h,m,s;
    pdf.HPDF_Open(2510,1000);
    pdf.HPDF_LoadTTFfont("/usr/share/SDL_UI/fonts/STSONG.TTF");
    pdf.HPDF_SampleTable(1,25,25,sample_format,0);

    g_Date.setTime(Date.now());
    if(g_using_UTC){
        year = g_Date.getUTCFullYear();
        mon = g_Date.getUTCMonth() + 1;
        dd = g_Date.getUTCDate();
        h = g_Date.getUTCHours();
        m = g_Date.getUTCMinutes();
        s = g_Date.getUTCSeconds();
    }
    else{
        year = g_Date.getFullYear();
        mon = g_Date.getMonth() + 1;
        dd = g_Date.getDate();
        h = g_Date.getHours();
        m = g_Date.getMinutes();
        s = g_Date.getSeconds();
    }
    var ret = pdf.HPDF_Save("/media/usb/" + "DATA_his" + "_" + year + "-" + mon + "-" + dd + "_" + h + "." + m + "." + s + ".pdf");
    pdf.HPDF_Close();
    if(ret == 1)
        Hmiregs.OpenPage(43,1);//导出成功
    else if(ret == 0)
        Hmiregs.OpenPage(44,1);
    else if(ret == -1)
        Hmiregs.OpenPage(45,1);
    Hmiregs.SetReg(0,3,62,0);
}
```

6 Functions related to CSV

Hmicsv.Create

Hmicsv.Create(filename): Scan devices and find the USB disk. Create a file named filename.

Hmicsv.Setup

Hmicsv.Setup(cloum, "selectcloum1, 2, 3, ...", row, ranked_cloum, rankey);

The following are the parameters-

cloum: number of columns to be exported. (The number of columns excluding No., date, and time when exporting sampling records; Total number of columns when exporting from database.)

"selectcloum1, 2, 3, ...": select fields to be exported corresponding to each column. (The first three columns of sampling are fixed as number, date, and

	time, so selectcloum1 is displayed in the fourth column. The sampling number and field number start from 1.) row: Maximum number of rows to export ranked_cloum: sort based on that column. (The column should be selected. That is, the column is selectcloum1, 2 or 3...) (This item cannot be 0) rankey: type of sorting. 0-don't sort; 1-int, smallest to largest; -1-int, largest to smallest; 2-float, smallest to largest; 3-double, smallest to largest; 4-string smallest to largest;
Hmicsv.SampleExport	SampleExport(format, stime, etime, method, val); format: Specify the format of each sid, separated by commas. stime,etime: starting time and end time to export records. method: 0-chronologically; n-by column n. val: export records where selectclonum n = val.
Hmicsv.AlarmExport	AlarmExport(stype, etype, source, stime, etime); stype, etype: starting and ending alarm type to be filtered. source: specified data source. 0: All alarms in the real-time buffer. 1: In the real-time buffer, the acknowledged alarms. 2: In the real-time buffer, the unacknowledged alarms. 3: In the real-time buffer, the alarms that do not require acknowledgment. 4: In the real-time buffer, the alarms that have been disarmed. 5: In the real-time buffer, the alarms that are not disarmed 6: In history, the acknowledged alarms. 7: In history, the unacknowledged alarms. 8: In history, the alarms that do not require acknowledgment. 9: In history, the alarms that have been disarmed. 10: In history, the alarms that are not disarmed. 11: All alarms in history. 12: All alarms in the real-time buffer and history. stime, etime: starting and ending time to export records (invalid in the current version)
Hmicsv.RecipeExport	RecipeExport(recipe_format,dbid); recipe_format: specify the format of every field, separated by commas. dbid: id of the exported database, starting from 0.
Hmicsv.Close()	Close corresponding source.

6.5 Reserved registers

In the local HMI device, some register addresses are reserved for special purposes, and these registers should be avoided when setting registers.

1 User account login


IS8202	To save the entered user name when logging in. See chapter 3.9 for details.
IS8214	To save the entered password when logging in. See chapter 3.9 for details.
IW8220	This register needs to be set when the user log in. See chapter 3.9 for details.

2. Others

QW8224	Save the communication with PLC: 0: PLC not connected. 1: Abnormal communication with PLC. 2: PLC running.
QB8224	Detect whether a USB disk is inserted: 0: No USB disk is inserted. 1: The USB disk is inserted.
QB8225	Detect whether a SD card is inserted: 0: No SD card is inserted. 1: The SD card is inserted.
IW8300	The currently operated recipe database.
IW8301	The selected record in the current recipe database.
IW8302	Enter a specific value to perform an operation and return the result of executing the command.
IW8303	Display the total number of records in the current recipe database.

6.6 Background settings

The background picture can be set separately for each window: double-click the selected window in the [window] list -> right-click in the window area -> [Background Settings] -> select the background image -> select the picture file -> click the [Save] icon in the left [window] interface. For files with the same name, you need to switch to another window and then switch back to refresh and display the new background image after setting. **(In the current version, you should set a background image or background color for each window. The background color cannot be transparent. It is recommended to use an image that fits the window size. Don't use a PNG image whose background is transparent. You can set as follows.**



Revision records

Rev	Revise Date	Content	Editor
00	2022-12-5	First Edition	Lvzhi Chen